

## NAME

perlapi - autogenerated documentation for the perl public API

## DESCRIPTION

This file contains the documentation of the perl public API generated by `embed.pl`, specifically a listing of functions, macros, flags, and variables that may be used by extension writers. The interfaces of any functions that are not listed here are subject to change without notice. For this reason, blindly using functions listed in `proto.h` is to be avoided when writing extensions.

Note that all Perl API global variables must be referenced with the `PL_` prefix. Some macros are provided for compatibility with the older, unadorned names, but this support may be disabled in a future release.

The listing is alphabetical, case insensitive.

## "Gimme" Values

### GIMME

A backward-compatible version of `GIMME_V` which can only return `G_SCALAR` or `G_ARRAY`; in a void context, it returns `G_SCALAR`. Deprecated. Use `GIMME_V` instead.

U32 GIMME

### GIMME\_V

The XSUB-writer's equivalent to Perl's `wantarray`. Returns `G_VOID`, `G_SCALAR` or `G_ARRAY` for void, scalar or list context, respectively.

U32 GIMME\_V

### G\_ARRAY

Used to indicate list context. See `GIMME_V`, `GIMME` and *percall*.

### G\_DISCARD

Indicates that arguments returned from a callback should be discarded. See *percall*.

### G\_EVAL

Used to force a Perl `eval` wrapper around a callback. See *percall*.

### G\_NOARGS

Indicates that no arguments are being sent to a callback. See *percall*.

### G\_SCALAR

Used to indicate scalar context. See `GIMME_V`, `GIMME`, and *percall*.

### G\_VOID

Used to indicate void context. See `GIMME_V` and *percall*.

## Array Manipulation Functions

### AvFILL

Same as `av_len()`. Deprecated, use `av_len()` instead.

```
int AvFILL(AV* av)
```

### av\_clear

Clears an array, making it empty. Does not free the memory used by the array itself.

```
void av_clear(AV* ar)
```

**av\_delete**

Deletes the element indexed by `key` from the array. Returns the deleted element. If `flags` equals `G_DISCARD`, the element is freed and null is returned.

```
SV* av_delete(AV* ar, I32 key, I32 flags)
```

**av\_exists**

Returns true if the element indexed by `key` has been initialized.

This relies on the fact that uninitialized array elements are set to `&PL_sv_undef`.

```
bool av_exists(AV* ar, I32 key)
```

**av\_extend**

Pre-extend an array. The `key` is the index to which the array should be extended.

```
void av_extend(AV* ar, I32 key)
```

**av\_fetch**

Returns the SV at the specified index in the array. The `key` is the index. If `lval` is set then the fetch will be part of a store. Check that the return value is non-null before dereferencing it to a SV\*.

See "*Understanding the Magic of Tied Hashes and Arrays*" in *perlguts* for more information on how to use this function on tied arrays.

```
SV** av_fetch(AV* ar, I32 key, I32 lval)
```

**av\_fill**

Ensure that an array has a given number of elements, equivalent to Perl's  `$#array = $fill;`

```
void av_fill(AV* ar, I32 fill)
```

**av\_len**

Returns the highest index in the array. Returns -1 if the array is empty.

```
I32 av_len(AV* ar)
```

**av\_make**

Creates a new AV and populates it with a list of SVs. The SVs are copied into the array, so they may be freed after the call to `av_make`. The new AV will have a reference count of 1.

```
AV* av_make(I32 size, SV** svp)
```

**av\_pop**

Pops an SV off the end of the array. Returns `&PL_sv_undef` if the array is empty.

```
SV* av_pop(AV* ar)
```

**av\_push**

Pushes an SV onto the end of the array. The array will grow automatically to accommodate the addition.

```
void av_push(AV* ar, SV* val)
```

**av\_shift**

Shifts an SV off the beginning of the array.

```
SV* av_shift(AV* ar)
```

**av\_store**

Stores an SV in an array. The array index is specified as `key`. The return value will be NULL if the operation failed or if the value did not need to be actually stored within the array (as in the case of tied arrays). Otherwise it can be dereferenced to get the original SV\*. Note that the caller is responsible for suitably incrementing the reference count of `val` before the call, and decrementing it if the function returned NULL.

See "*Understanding the Magic of Tied Hashes and Arrays*" in *perlguts* for more information on how to use this function on tied arrays.

```
SV** av_store(AV* ar, I32 key, SV* val)
```

**av\_undef**

Undefines the array. Frees the memory used by the array itself.

```
void av_undef(AV* ar)
```

**av\_unshift**

Unshift the given number of `undef` values onto the beginning of the array. The array will grow automatically to accommodate the addition. You must then use `av_store` to assign values to these new elements.

```
void av_unshift(AV* ar, I32 num)
```

**get\_av**

Returns the AV of the specified Perl array. If `create` is set and the Perl variable does not exist then it will be created. If `create` is not set and the variable does not exist then NULL is returned.

NOTE: the `perl_` form of this function is deprecated.

```
AV* get_av(const char* name, I32 create)
```

**newAV**

Creates a new AV. The reference count is set to 1.

```
AV* newAV()
```

**sortsv**

Sort an array. Here is an example:

```
sortsv(AvARRAY(av), av_len(av)+1, Perl_sv_cmp_locale);
```

See `lib/sort.pm` for details about controlling the sorting algorithm.

```
void sortsv(SV** array, size_t num_elts, SVCOMPARE_t cmp)
```

## Callback Functions

**call\_argv**

Performs a callback to the specified Perl sub. See *perlcall*.

NOTE: the `perl_` form of this function is deprecated.

```
I32 call_argv(const char* sub_name, I32 flags, char** argv)
```

**call\_method**

Performs a callback to the specified Perl method. The blessed object must be on the stack. See *percall*.

NOTE: the `perl_` form of this function is deprecated.

```
I32 call_method(const char* methname, I32 flags)
```

**call\_pv**

Performs a callback to the specified Perl sub. See *percall*.

NOTE: the `perl_` form of this function is deprecated.

```
I32 call_pv(const char* sub_name, I32 flags)
```

**call\_sv**

Performs a callback to the Perl sub whose name is in the SV. See *percall*.

NOTE: the `perl_` form of this function is deprecated.

```
I32 call_sv(SV* sv, I32 flags)
```

**ENTER**

Opening bracket on a callback. See `LEAVE` and *percall*.

```
ENTER;
```

**eval\_pv**

Tells Perl to `eval` the given string and return an SV\* result.

NOTE: the `perl_` form of this function is deprecated.

```
SV* eval_pv(const char* p, I32 croak_on_error)
```

**eval\_sv**

Tells Perl to `eval` the string in the SV.

NOTE: the `perl_` form of this function is deprecated.

```
I32 eval_sv(SV* sv, I32 flags)
```

**FREETMPS**

Closing bracket for temporaries on a callback. See `SAVETMPS` and *percall*.

```
FREETMPS;
```

**LEAVE**

Closing bracket on a callback. See `ENTER` and *percall*.

```
LEAVE;
```

**SAVETMPS**

Opening bracket for temporaries on a callback. See `FREETMPS` and *percall*.

```
SAVETMPS;
```

**Character classes****isALNUM**

Returns a boolean indicating whether the C `char` is an ASCII alphanumeric character

(including underscore) or digit.

```
bool isALNUM(char ch)
```

#### isALPHA

Returns a boolean indicating whether the C `char` is an ASCII alphabetic character.

```
bool isALPHA(char ch)
```

#### isDIGIT

Returns a boolean indicating whether the C `char` is an ASCII digit.

```
bool isDIGIT(char ch)
```

#### isLOWER

Returns a boolean indicating whether the C `char` is a lowercase character.

```
bool isLOWER(char ch)
```

#### isSPACE

Returns a boolean indicating whether the C `char` is whitespace.

```
bool isSPACE(char ch)
```

#### isUPPER

Returns a boolean indicating whether the C `char` is an uppercase character.

```
bool isUPPER(char ch)
```

#### toLOWER

Converts the specified character to lowercase.

```
char toLOWER(char ch)
```

#### toUPPER

Converts the specified character to uppercase.

```
char toUPPER(char ch)
```

## Cloning an interpreter

### perl\_clone

Create and return a new interpreter by cloning the current one.

`perl_clone` takes these flags as parameters:

`CLONEf_COPY_STACKS` - is used to, well, copy the stacks also, without it we only clone the data and zero the stacks, with it we copy the stacks and the new perl interpreter is ready to run at the exact same point as the previous one. The pseudo-fork code uses `COPY_STACKS` while the `threads->new` doesn't.

`CLONEf_KEEP_PTR_TABLE` `perl_clone` keeps a `ptr_table` with the pointer of the old variable as a key and the new variable as a value, this allows it to check if something has been cloned and not clone it again but rather just use the value and increase the refcount. If `KEEP_PTR_TABLE` is not set then `perl_clone` will kill the `ptr_table` using the function `ptr_table_free(PL_ptr_table); PL_ptr_table = NULL;`, reason to keep it around is if you want to dup some of your own variable who are outside the graph perl scans, example of this code is in `threads.xs` create

`CLONEf_CLONE_HOST` This is a win32 thing, it is ignored on unix, it tells perls win32host code (which is c++) to clone itself, this is needed on win32 if you want to run two threads at the same time, if you just want to do some stuff in a separate perl interpreter and then throw it away and return to the original one, you don't need to do anything.

```
PerlInterpreter* perl_clone(PerlInterpreter* interp, UV flags)
```

## CV Manipulation Functions

### `CvSTASH`

Returns the stash of the CV.

```
HV* CvSTASH(CV* cv)
```

### `get_cv`

Returns the CV of the specified Perl subroutine. If `create` is set and the Perl subroutine does not exist then it will be declared (which has the same effect as saying `sub name;`). If `create` is not set and the subroutine does not exist then NULL is returned.

NOTE: the `perl_` form of this function is deprecated.

```
CV* get_cv(const char* name, I32 create)
```

## Embedding Functions

### `cv_undef`

Clear out all the active components of a CV. This can happen either by an explicit `undef &foo`, or by the reference count going to zero. In the former case, we keep the `CvOUTSIDE` pointer, so that any anonymous children can still follow the full lexical scope chain.

```
void cv_undef(CV* cv)
```

### `load_module`

Loads the module whose name is pointed to by the string part of `name`. Note that the actual module name, not its filename, should be given. Eg, "Foo::Bar" instead of "Foo/Bar.pm". `flags` can be any of `PERL_LOADMOD_DENY`, `PERL_LOADMOD_NOIMPORT`, or `PERL_LOADMOD_IMPORT_OPS` (or 0 for no flags). `ver`, if specified, provides version semantics similar to `use Foo::Bar VERSION`. The optional trailing `SV*` arguments can be used to specify arguments to the module's `import()` method, similar to `use Foo::Bar VERSION LIST`.

```
void load_module(U32 flags, SV* name, SV* ver, ...)
```

### `nothreadhook`

Stub that provides thread hook for `perl_destruct` when there are no threads.

```
int nothreadhook()
```

### `perl_alloc`

Allocates a new Perl interpreter. See *perlembed*.

```
PerlInterpreter* perl_alloc()
```

### `perl_construct`

Initializes a new Perl interpreter. See *perlembed*.

```
void perl_construct(PerlInterpreter* interp)
```

#### perl\_destruct

Shuts down a Perl interpreter. See *perlembd*.

```
int perl_destruct(PerlInterpreter* interp)
```

#### perl\_free

Releases a Perl interpreter. See *perlembd*.

```
void perl_free(PerlInterpreter* interp)
```

#### perl\_parse

Tells a Perl interpreter to parse a Perl script. See *perlembd*.

```
int perl_parse(PerlInterpreter* interp, XSINIT_t xsinit, int  
argc, char** argv, char** env)
```

#### perl\_run

Tells a Perl interpreter to run. See *perlembd*.

```
int perl_run(PerlInterpreter* interp)
```

#### require\_pv

Tells Perl to *require* the file named by the string argument. It is analogous to the Perl code `eval "require '$file'".` It's even implemented that way; consider using `load_module` instead.

NOTE: the `perl_` form of this function is deprecated.

```
void require_pv(const char* pv)
```

## Functions in file `pp_pack.c`

#### packlist

The engine implementing `pack()` Perl function.

```
void packlist(SV *cat, char *pat, char *patend, SV **beglist,  
SV **endlist)
```

#### pack\_cat

The engine implementing `pack()` Perl function. Note: parameters `next_in_list` and `flags` are not used. This call should not be used; use `packlist` instead.

```
void pack_cat(SV *cat, char *pat, char *patend, SV **beglist,  
SV **endlist, SV ***next_in_list, U32 flags)
```

#### unpackstring

The engine implementing `unpack()` Perl function. `unpackstring` puts the extracted list items on the stack and returns the number of elements. Issue `PUTBACK` before and `SPAGAIN` after the call to this function.

```
I32 unpackstring(char *pat, char *patend, char *s, char  
*strend, U32 flags)
```

#### unpack\_str

The engine implementing `unpack()` Perl function. Note: parameters `strbeg`, `new_s` and

ocnt are not used. This call should not be used, use `unpackstring` instead.

```
I32 unpack_str(char *pat, char *patend, char *s, char *strbeg,
char *strend, char **new_s, I32 ocnt, U32 flags)
```

## Global Variables

### PL\_modglobal

`PL_modglobal` is a general purpose, interpreter global HV for use by extensions that need to keep information on a per-interpreter basis. In a pinch, it can also be used as a symbol table for extensions to share data among each other. It is a good idea to use keys prefixed by the package name of the extension that owns the data.

```
HV* PL_modglobal
```

### PL\_na

A convenience variable which is typically used with `SvPV` when one doesn't care about the length of the string. It is usually more efficient to either declare a local variable and use that instead or to use the `SvPV_nolen` macro.

```
STRLEN PL_na
```

### PL\_sv\_no

This is the `false` SV. See `PL_sv_yes`. Always refer to this as `&PL_sv_no`.

```
SV PL_sv_no
```

### PL\_sv\_undef

This is the `undef` SV. Always refer to this as `&PL_sv_undef`.

```
SV PL_sv_undef
```

### PL\_sv\_yes

This is the `true` SV. See `PL_sv_no`. Always refer to this as `&PL_sv_yes`.

```
SV PL_sv_yes
```

## GV Functions

### GvSV

Return the SV from the GV.

```
SV* GvSV(GV* gv)
```

### gv\_fetchmeth

Returns the glob with the given `name` and a defined subroutine or `NULL`. The glob lives in the given `stash`, or in the stashes accessible via `@ISA` and `UNIVERSAL::`.

The argument `level` should be either 0 or -1. If `level==0`, as a side-effect creates a glob with the given `name` in the given `stash` which in the case of success contains an alias for the subroutine, and sets up caching info for this glob. Similarly for all the searched stashes.

This function grants "SUPER" token as a postfix of the stash name. The GV returned from `gv_fetchmeth` may be a method cache entry, which is not visible to Perl code. So when calling `call_sv`, you should not use the GV directly; instead, you should use the method's CV, which can be obtained from the GV with the `GvCV` macro.

```
GV* gv_fetchmeth(HV* stash, const char* name, STRLEN len, I32
```



`gv_fetchmethod(level)`

See `gv_fetchmethod_autoload`.

```
GV* gv_fetchmethod(HV* stash, const char* name)
```

`gv_fetchmethod_autoload`

Returns the glob which contains the subroutine to call to invoke the method on the `stash`. In fact in the presence of autoloading this may be the glob for "AUTOLOAD". In this case the corresponding variable `$AUTOLOAD` is already setup.

The third parameter of `gv_fetchmethod_autoload` determines whether AUTOLOAD lookup is performed if the given method is not present: non-zero means yes, look for AUTOLOAD; zero means no, don't look for AUTOLOAD. Calling `gv_fetchmethod` is equivalent to calling `gv_fetchmethod_autoload` with a non-zero `autoload` parameter.

These functions grant "SUPER" token as a prefix of the method name. Note that if you want to keep the returned glob for a long time, you need to check for it being "AUTOLOAD", since at the later time the call may load a different subroutine due to `$AUTOLOAD` changing its value. Use the glob created via a side effect to do this.

These functions have the same side-effects and as `gv_fetchmeth` with `level==0`. `name` should be writable if contains ':' or ' '. The warning against passing the GV returned by `gv_fetchmeth` to `call_sv` apply equally to these functions.

```
GV* gv_fetchmethod_autoload(HV* stash, const char* name, I32
autoload)
```

`gv_fetchmeth_autoload`

Same as `gv_fetchmeth()`, but looks for autoloading subroutines too. Returns a glob for the subroutine.

For an autoloading subroutine without a GV, will create a GV even if `level < 0`. For an autoloading subroutine without a stub, `GvCV()` of the result may be zero.

```
GV* gv_fetchmeth_autoload(HV* stash, const char* name, STRLEN
len, I32 level)
```

`gv_stashpv`

Returns a pointer to the stash for a specified package. `name` should be a valid UTF-8 string and must be null-terminated. If `create` is set then the package will be created if it does not already exist. If `create` is not set and the package does not exist then NULL is returned.

```
HV* gv_stashpv(const char* name, I32 create)
```

`gv_stashpvn`

Returns a pointer to the stash for a specified package. `name` should be a valid UTF-8 string. The `namelen` parameter indicates the length of the name, in bytes. If `create` is set then the package will be created if it does not already exist. If `create` is not set and the package does not exist then NULL is returned.

```
HV* gv_stashpvn(const char* name, U32 namelen, I32 create)
```

`gv_stashsv`

Returns a pointer to the stash for a specified package, which must be a valid UTF-8 string. See `gv_stashpv`.

```
HV* gv_stashsv(SV* sv, I32 create)
```

## Handy Values

Nullav	Null AV pointer.
Nullch	Null character pointer.
Nullcv	Null CV pointer.
Nullhv	Null HV pointer.
Nullsv	Null SV pointer.

## Hash Manipulation Functions

### get\_hv

Returns the HV of the specified Perl hash. If `create` is set and the Perl variable does not exist then it will be created. If `create` is not set and the variable does not exist then NULL is returned.

NOTE: the `perl_` form of this function is deprecated.

```
HV* get_hv(const char* name, I32 create)
```

### HEf\_SVKEY

This flag, used in the length slot of hash entries and magic structures, specifies the structure contains an `SV*` pointer where a `char*` pointer is to be expected. (For information only--not to be used).

### HeHASH

Returns the computed hash stored in the hash entry.

```
U32 HeHASH(HE* he)
```

### HeKEY

Returns the actual pointer stored in the key slot of the hash entry. The pointer may be either `char*` or `SV*`, depending on the value of `HeKLEN()`. Can be assigned to. The `HePV()` or `HeSVKEY()` macros are usually preferable for finding the value of a key.

```
void* HeKEY(HE* he)
```

### HeKLEN

If this is negative, and amounts to `HEf_SVKEY`, it indicates the entry holds an `SV*` key. Otherwise, holds the actual length of the key. Can be assigned to. The `HePV()` macro is usually preferable for finding key lengths.

```
STRLEN HeKLEN(HE* he)
```

### HePV

Returns the key slot of the hash entry as a `char*` value, doing any necessary dereferencing of possibly `SV*` keys. The length of the string is placed in `len` (this is a macro, so do *not* use `&len`). If you do not care about what the length of the key is, you may use the global variable `PL_na`, though this is rather less efficient than using a local variable. Remember though, that hash keys in perl are free to contain embedded

nulls, so using `strlen()` or similar is not a good way to find the length of hash keys. This is very similar to the `SvPV()` macro described elsewhere in this document.

```
char* HePV(HE* he, STRLEN len)
```

#### HeSVKEY

Returns the key as an `SV*`, or `Nullsv` if the hash entry does not contain an `SV*` key.

```
SV* HeSVKEY(HE* he)
```

#### HeSVKEY\_force

Returns the key as an `SV*`. Will create and return a temporary mortal `SV*` if the hash entry contains only a `char*` key.

```
SV* HeSVKEY_force(HE* he)
```

#### HeSVKEY\_set

Sets the key to a given `SV*`, taking care to set the appropriate flags to indicate the presence of an `SV*` key, and returns the same `SV*`.

```
SV* HeSVKEY_set(HE* he, SV* sv)
```

#### HeVAL

Returns the value slot (type `SV*`) stored in the hash entry.

```
SV* HeVAL(HE* he)
```

#### HvNAME

Returns the package name of a stash. See `SvSTASH`, `CvSTASH`.

```
char* HvNAME(HV* stash)
```

#### hv\_clear

Clears a hash, making it empty.

```
void hv_clear(HV* tb)
```

#### hv\_clear\_placeholders

Clears any placeholders from a hash. If a restricted hash has any of its keys marked as readonly and the key is subsequently deleted, the key is not actually deleted but is marked by assigning it a value of `&PL_sv_placeholder`. This tags it so it will be ignored by future operations such as iterating over the hash, but will still allow the hash to have a value reassigned to the key at some future point. This function clears any such placeholder keys from the hash. See `Hash::Util::lock_keys()` for an example of its use.

```
void hv_clear_placeholders(HV* hb)
```

#### hv\_delete

Deletes a key/value pair in the hash. The value `SV` is removed from the hash and returned to the caller. The `klen` is the length of the key. The `flags` value will normally be zero; if set to `G_DISCARD` then `NULL` will be returned.

```
SV* hv_delete(HV* tb, const char* key, I32 klen, I32 flags)
```

#### hv\_delete\_ent

Deletes a key/value pair in the hash. The value `SV` is removed from the hash and

returned to the caller. The `flags` value will normally be zero; if set to `G_DISCARD` then `NULL` will be returned. `hash` can be a valid precomputed hash value, or 0 to ask for it to be computed.

```
SV* hv_delete_ent(HV* tb, SV* key, I32 flags, U32 hash)
```

#### hv\_exists

Returns a boolean indicating whether the specified hash key exists. The `klen` is the length of the key.

```
bool hv_exists(HV* tb, const char* key, I32 klen)
```

#### hv\_exists\_ent

Returns a boolean indicating whether the specified hash key exists. `hash` can be a valid precomputed hash value, or 0 to ask for it to be computed.

```
bool hv_exists_ent(HV* tb, SV* key, U32 hash)
```

#### hv\_fetch

Returns the `SV` which corresponds to the specified key in the hash. The `klen` is the length of the key. If `lval` is set then the fetch will be part of a store. Check that the return value is non-null before dereferencing it to an `SV*`.

See *"Understanding the Magic of Tied Hashes and Arrays" in perlguits* for more information on how to use this function on tied hashes.

```
SV** hv_fetch(HV* tb, const char* key, I32 klen, I32 lval)
```

#### hv\_fetch\_ent

Returns the hash entry which corresponds to the specified key in the hash. `hash` must be a valid precomputed hash number for the given `key`, or 0 if you want the function to compute it. IF `lval` is set then the fetch will be part of a store. Make sure the return value is non-null before accessing it. The return value when `tb` is a tied hash is a pointer to a static location, so be sure to make a copy of the structure if you need to store it somewhere.

See *"Understanding the Magic of Tied Hashes and Arrays" in perlguits* for more information on how to use this function on tied hashes.

```
HE* hv_fetch_ent(HV* tb, SV* key, I32 lval, U32 hash)
```

#### hv\_iterinit

Prepares a starting point to traverse a hash table. Returns the number of keys in the hash (i.e. the same as `HvKEYS(tb)`). The return value is currently only meaningful for hashes without tie magic.

NOTE: Before version 5.004\_65, `hv_iterinit` used to return the number of hash buckets that happen to be in use. If you still need that esoteric value, you can get it through the macro `HvFILL(tb)`.

```
I32 hv_iterinit(HV* tb)
```

#### hv\_iterkey

Returns the key from the current position of the hash iterator. See `hv_iterinit`.

```
char* hv_iterkey(HE* entry, I32* retlen)
```

#### hv\_iterkeysv

Returns the key as an `SV*` from the current position of the hash iterator. The return value will always be a mortal copy of the key. Also see `hv_iterinit`.

```
SV* hv_iterkeysv(HE* entry)
```

#### `hv_iternext`

Returns entries from a hash iterator. See `hv_iterinit`.

You may call `hv_delete` or `hv_delete_ent` on the hash entry that the iterator currently points to, without losing your place or invalidating your iterator. Note that in this case the current entry is deleted from the hash with your iterator holding the last reference to it. Your iterator is flagged to free the entry on the next call to `hv_iternext`, so you must not discard your iterator immediately else the entry will leak - call `hv_iternext` to trigger the resource deallocation.

```
HE* hv_iternext(HV* tb)
```

#### `hv_iternextsv`

Performs an `hv_iternext`, `hv_iterkey`, and `hv_interval` in one operation.

```
SV* hv_iternextsv(HV* hv, char** key, I32* retlen)
```

#### `hv_iternext_flags`

Returns entries from a hash iterator. See `hv_iterinit` and `hv_iternext`. The `flags` value will normally be zero; if `HV_ITERNEXT_WANTPLACEHOLDERS` is set the placeholders keys (for restricted hashes) will be returned in addition to normal keys. By default placeholders are automatically skipped over. Currently a placeholder is implemented with a value that is `&Perl_sv_placeholder`. Note that the implementation of placeholders and restricted hashes may change, and the implementation currently is insufficiently abstracted for any change to be tidy.

NOTE: this function is experimental and may change or be removed without notice.

```
HE* hv_iternext_flags(HV* tb, I32 flags)
```

#### `hv_interval`

Returns the value from the current position of the hash iterator. See `hv_iterkey`.

```
SV* hv_interval(HV* tb, HE* entry)
```

#### `hv_magic`

Adds magic to a hash. See `sv_magic`.

```
void hv_magic(HV* hv, GV* gv, int how)
```

#### `hv_scalar`

Evaluates the hash in scalar context and returns the result. Handles magic when the hash is tied.

```
SV* hv_scalar(HV* hv)
```

#### `hv_store`

Stores an `SV` in a hash. The hash key is specified as `key` and `klen` is the length of the key. The `hash` parameter is the precomputed hash value; if it is zero then Perl will compute it. The return value will be `NULL` if the operation failed or if the value did not need to be actually stored within the hash (as in the case of tied hashes). Otherwise it can be dereferenced to get the original `SV*`. Note that the caller is responsible for

suitably incrementing the reference count of `val` before the call, and decrementing it if the function returned `NULL`. Effectively a successful `hv_store` takes ownership of one reference to `val`. This is usually what you want; a newly created SV has a reference count of one, so if all your code does is create SVs then store them in a hash, `hv_store` will own the only reference to the new SV, and your code doesn't need to do anything further to tidy up. `hv_store` is not implemented as a call to `hv_store_ent`, and does not create a temporary SV for the key, so if your key data is not already in SV form then use `hv_store` in preference to `hv_store_ent`.

See "*Understanding the Magic of Tied Hashes and Arrays*" in *perlguts* for more information on how to use this function on tied hashes.

```
SV** hv_store(HV* tb, const char* key, I32 klen, SV* val, U32
hash)
```

### hv\_store\_ent

Stores `val` in a hash. The hash key is specified as `key`. The `hash` parameter is the precomputed hash value; if it is zero then Perl will compute it. The return value is the new hash entry so created. It will be `NULL` if the operation failed or if the value did not need to be actually stored within the hash (as in the case of tied hashes). Otherwise the contents of the return value can be accessed using the `He?` macros described here. Note that the caller is responsible for suitably incrementing the reference count of `val` before the call, and decrementing it if the function returned `NULL`. Effectively a successful `hv_store_ent` takes ownership of one reference to `val`. This is usually what you want; a newly created SV has a reference count of one, so if all your code does is create SVs then store them in a hash, `hv_store` will own the only reference to the new SV, and your code doesn't need to do anything further to tidy up. Note that `hv_store_ent` only reads the `key`; unlike `val` it does not take ownership of it, so maintaining the correct reference count on `key` is entirely the caller's responsibility. `hv_store` is not implemented as a call to `hv_store_ent`, and does not create a temporary SV for the key, so if your key data is not already in SV form then use `hv_store` in preference to `hv_store_ent`.

See "*Understanding the Magic of Tied Hashes and Arrays*" in *perlguts* for more information on how to use this function on tied hashes.

```
HE* hv_store_ent(HV* tb, SV* key, SV* val, U32 hash)
```

### hv\_undef

Undefines the hash.

```
void hv_undef(HV* tb)
```

### newHV

Creates a new HV. The reference count is set to 1.

```
HV* newHV()
```

## Magical Functions

### mg\_clear

Clear something magical that the SV represents. See *sv\_magic*.

```
int mg_clear(SV* sv)
```

### mg\_copy

Copies the magic from one SV to another. See *sv\_magic*.

```
int mg_copy(SV* sv, SV* nsv, const char* key, I32 klen)
```

**mg\_find**

Finds the magic pointer for type matching the SV. See `sv_magic`.

```
MAGIC* mg_find(SV* sv, int type)
```

**mg\_free**

Free any magic storage used by the SV. See `sv_magic`.

```
int mg_free(SV* sv)
```

**mg\_get**

Do magic after a value is retrieved from the SV. See `sv_magic`.

```
int mg_get(SV* sv)
```

**mg\_length**

Report on the SV's length. See `sv_magic`.

```
U32 mg_length(SV* sv)
```

**mg\_magical**

Turns on the magical status of an SV. See `sv_magic`.

```
void mg_magical(SV* sv)
```

**mg\_set**

Do magic after a value is assigned to the SV. See `sv_magic`.

```
int mg_set(SV* sv)
```

**SvGETMAGIC**

Invokes `mg_get` on an SV if it has 'get' magic. This macro evaluates its argument more than once.

```
void SvGETMAGIC(SV* sv)
```

**SvLOCK**

Arranges for a mutual exclusion lock to be obtained on `sv` if a suitable module has been loaded.

```
void SvLOCK(SV* sv)
```

**SvSETMAGIC**

Invokes `mg_set` on an SV if it has 'set' magic. This macro evaluates its argument more than once.

```
void SvSETMAGIC(SV* sv)
```

**SvSetMagicSV**

Like `SvSetSV`, but does any set magic required afterwards.

```
void SvSetMagicSV(SV* dsb, SV* ssv)
```

**SvSetMagicSV\_nosteal**

Like `SvSetSV_nosteal`, but does any set magic required afterwards.

```
void SvSetMagicSV_nosteal(SV* dsv, SV* ssv)
```

### SvSetSV

Calls `sv_setsv` if `dsv` is not the same as `ssv`. May evaluate arguments more than once.

```
void SvSetSV(SV* dsb, SV* ssv)
```

### SvSetSV\_nosteal

Calls a non-destructive version of `sv_setsv` if `dsv` is not the same as `ssv`. May evaluate arguments more than once.

```
void SvSetSV_nosteal(SV* dsv, SV* ssv)
```

### SvSHARE

Arranges for `sv` to be shared between threads if a suitable module has been loaded.

```
void SvSHARE(SV* sv)
```

### SvUNLOCK

Releases a mutual exclusion lock on `sv` if a suitable module has been loaded.

```
void SvUNLOCK(SV* sv)
```

## Memory Management

### Copy

The XSUB-writer's interface to the C `memcpy` function. The `src` is the source, `dest` is the destination, `nitems` is the number of items, and `type` is the type. May fail on overlapping copies. See also `Move`.

```
void Copy(void* src, void* dest, int nitems, type)
```

### CopyD

Like `Copy` but returns `dest`. Useful for encouraging compilers to tail-call optimise.

```
void * CopyD(void* src, void* dest, int nitems, type)
```

### Move

The XSUB-writer's interface to the C `memmove` function. The `src` is the source, `dest` is the destination, `nitems` is the number of items, and `type` is the type. Can do overlapping moves. See also `Copy`.

```
void Move(void* src, void* dest, int nitems, type)
```

### MoveD

Like `Move` but returns `dest`. Useful for encouraging compilers to tail-call optimise.

```
void * MoveD(void* src, void* dest, int nitems, type)
```

### Newx

The XSUB-writer's interface to the C `malloc` function.

```
void Newx(void* ptr, int nitems, type)
```

### Newxc



The XSUB-writer's interface to the C `malloc` function, with cast.

```
void Newxc(void* ptr, int nitems, type, cast)
```

#### Newxz

The XSUB-writer's interface to the C `malloc` function. The allocated memory is zeroed with `memzero`.

In 5.9.3, we removed the 1st parameter, a debug aid, from the api. It was used to uniquely identify each usage of these allocation functions, but was deemed unnecessary with the availability of better memory tracking tools, `valgrind` for example.

```
void Newxz(void* ptr, int nitems, type)
```

#### Poison

Fill up memory with a pattern (byte 0xAB over and over again) that hopefully catches attempts to access uninitialized memory.

```
void Poison(void* dest, int nitems, type)
```

#### Renew

The XSUB-writer's interface to the C `realloc` function.

```
void Renew(void* ptr, int nitems, type)
```

#### Renewc

The XSUB-writer's interface to the C `realloc` function, with cast.

```
void Renewc(void* ptr, int nitems, type, cast)
```

#### Safefree

The XSUB-writer's interface to the C `free` function.

```
void Safefree(void* ptr)
```

#### savepv

Perl's version of `strdup()`. Returns a pointer to a newly allocated string which is a duplicate of `pv`. The size of the string is determined by `strlen()`. The memory allocated for the new string can be freed with the `Safefree()` function.

```
char* savepv(const char* pv)
```

#### savepvn

Perl's version of what `strndup()` would be if it existed. Returns a pointer to a newly allocated string which is a duplicate of the first `len` bytes from `pv`. The memory allocated for the new string can be freed with the `Safefree()` function.

```
char* savepvn(const char* pv, I32 len)
```

#### savesharedpv

A version of `savepv()` which allocates the duplicate string in memory which is shared between threads.

```
char* savesharedpv(const char* pv)
```

#### savesvpv

A version of `savepv()`/`savepvn()` which gets the string to duplicate from the passed

in SV using `SvPV()`

```
char* savesvpv(SV* sv)
```

### StructCopy

This is an architecture-independent macro to copy one structure to another.

```
void StructCopy(type src, type dest, type)
```

### Zero

The XSUB-writer's interface to the C `memzero` function. The `dest` is the destination, `nitems` is the number of items, and `type` is the type.

```
void Zero(void* dest, int nitems, type)
```

### ZeroD

Like `Zero` but returns `dest`. Useful for encouraging compilers to tail-call optimise.

```
void * ZeroD(void* dest, int nitems, type)
```

## Miscellaneous Functions

### fbm\_compile

Analyses the string in order to make fast searches on it using `fbm_instr()` -- the Boyer-Moore algorithm.

```
void fbm_compile(SV* sv, U32 flags)
```

### fbm\_instr

Returns the location of the SV in the string delimited by `str` and `strend`. It returns `Nullch` if the string can't be found. The `sv` does not have to be `fbm_compiled`, but the search will not be as fast then.

```
char* fbm_instr(unsigned char* big, unsigned char* bigend, SV*  
littlesv, U32 flags)
```

### form

Takes a `sprintf`-style format pattern and conventional (non-SV) arguments and returns the formatted string.

```
(char *) Perl_form(pTHX_ const char* pat, ...)
```

can be used any place a string (`char *`) is required:

```
char * s = Perl_form("%d.%d",major,minor);
```

Uses a single private buffer so if you want to format several strings you must explicitly copy the earlier strings away (and free the copies when you are done).

```
char* form(const char* pat, ...)
```

### getcwd\_sv

Fill the `sv` with current working directory

```
int getcwd_sv(SV* sv)
```

### strEQ

Test two strings to see if they are equal. Returns true or false.

```
bool strEQ(char* s1, char* s2)
```

### strGE

Test two strings to see if the first, *s1*, is greater than or equal to the second, *s2*. Returns true or false.

```
bool strGE(char* s1, char* s2)
```

### strGT

Test two strings to see if the first, *s1*, is greater than the second, *s2*. Returns true or false.

```
bool strGT(char* s1, char* s2)
```

### strLE

Test two strings to see if the first, *s1*, is less than or equal to the second, *s2*. Returns true or false.

```
bool strLE(char* s1, char* s2)
```

### strLT

Test two strings to see if the first, *s1*, is less than the second, *s2*. Returns true or false.

```
bool strLT(char* s1, char* s2)
```

### strNE

Test two strings to see if they are different. Returns true or false.

```
bool strNE(char* s1, char* s2)
```

### strnEQ

Test two strings to see if they are equal. The *len* parameter indicates the number of bytes to compare. Returns true or false. (A wrapper for `strncmp`).

```
bool strnEQ(char* s1, char* s2, STRLEN len)
```

### strnNE

Test two strings to see if they are different. The *len* parameter indicates the number of bytes to compare. Returns true or false. (A wrapper for `strncmp`).

```
bool strnNE(char* s1, char* s2, STRLEN len)
```

### sv\_nolocking

Dummy routine which "locks" an SV when there is no locking module present. Exists to avoid test for a NULL function pointer and because it could potentially warn under some level of strict-ness.

```
void sv_nolocking(SV *)
```

### sv\_nosharing

Dummy routine which "shares" an SV when there is no sharing module present. Exists to avoid test for a NULL function pointer and because it could potentially warn under some level of strict-ness.

```
void sv_nosharing(SV *)
```

## sv\_nounlocking

Dummy routine which "unlocks" an SV when there is no locking module present. Exists to avoid test for a NULL function pointer and because it could potentially warn under some level of strict-ness.

```
void sv_nounlocking(SV *)
```

## Numeric functions

## grok\_bin

converts a string representing a binary number to numeric form.

On entry *start* and *\*len* give the string to scan, *\*flags* gives conversion flags, and *result* should be NULL or a pointer to an NV. The scan stops at the end of the string, or the first invalid character. Unless `PERL_SCAN_SILENT_ILLDIGIT` is set in *\*flags*, encountering an invalid character will also trigger a warning. On return *\*len* is set to the length of the scanned string, and *\*flags* gives output flags.

If the value is  $\leq$  UV\_MAX it is returned as a UV, the output flags are clear, and nothing is written to *\*result*. If the value is  $>$  UV\_MAX `grok_bin` returns UV\_MAX, sets `PERL_SCAN_GREATER_THAN_UV_MAX` in the output flags, and writes the value to *\*result* (or the value is discarded if *result* is NULL).

The binary number may optionally be prefixed with "0b" or "b" unless `PERL_SCAN_DISALLOW_PREFIX` is set in *\*flags* on entry. If `PERL_SCAN_ALLOW_UNDERSCORES` is set in *\*flags* then the binary number may use '\_' characters to separate digits.

```
UV grok_bin(char* start, STRLEN* len, I32* flags, NV *result)
```

## grok\_hex

converts a string representing a hex number to numeric form.

On entry *start* and *\*len* give the string to scan, *\*flags* gives conversion flags, and *result* should be NULL or a pointer to an NV. The scan stops at the end of the string, or the first invalid character. Unless `PERL_SCAN_SILENT_ILLDIGIT` is set in *\*flags*, encountering an invalid character will also trigger a warning. On return *\*len* is set to the length of the scanned string, and *\*flags* gives output flags.

If the value is  $\leq$  UV\_MAX it is returned as a UV, the output flags are clear, and nothing is written to *\*result*. If the value is  $>$  UV\_MAX `grok_hex` returns UV\_MAX, sets `PERL_SCAN_GREATER_THAN_UV_MAX` in the output flags, and writes the value to *\*result* (or the value is discarded if *result* is NULL).

The hex number may optionally be prefixed with "0x" or "x" unless `PERL_SCAN_DISALLOW_PREFIX` is set in *\*flags* on entry. If `PERL_SCAN_ALLOW_UNDERSCORES` is set in *\*flags* then the hex number may use '\_' characters to separate digits.

```
UV grok_hex(char* start, STRLEN* len, I32* flags, NV *result)
```

## grok\_number

Recognise (or not) a number. The type of the number is returned (0 if unrecognised), otherwise it is a bit-ORed combination of `IS_NUMBER_IN_UV`, `IS_NUMBER_GREATER_THAN_UV_MAX`, `IS_NUMBER_NOT_INT`, `IS_NUMBER_NEG`, `IS_NUMBER_INFINITY`, `IS_NUMBER_NAN` (defined in perl.h).

If the value of the number can fit in UV, it is returned in the *\*valuep*. `IS_NUMBER_IN_UV` will be set to indicate that *\*valuep* is valid, `IS_NUMBER_IN_UV` will never be set unless *\*valuep* is valid, but *\*valuep* may have been assigned to during processing even though `IS_NUMBER_IN_UV` is not set on return. If *valuep* is NULL,

IS\_NUMBER\_IN\_UV will be set for the same cases as when `valuep` is non-NULL, but no actual assignment (or SEGV) will occur.

IS\_NUMBER\_NOT\_INT will be set with IS\_NUMBER\_IN\_UV if trailing decimals were seen (in which case `*valuep` gives the true value truncated to an integer), and IS\_NUMBER\_NEG if the number is negative (in which case `*valuep` holds the absolute value). IS\_NUMBER\_IN\_UV is not set if e notation was used or the number is larger than a UV.

```
int grok_number(const char *pv, STRLEN len, UV *valuep)
```

#### grok\_numeric\_radix

Scan and skip for a numeric decimal separator (radix).

```
bool grok_numeric_radix(const char **sp, const char *send)
```

#### grok\_oct

converts a string representing an octal number to numeric form.

On entry `start` and `*len` give the string to scan, `*flags` gives conversion flags, and `result` should be NULL or a pointer to an NV. The scan stops at the end of the string, or the first invalid character. Unless PERL\_SCAN\_SILENT\_ILLDIGIT is set in `*flags`, encountering an invalid character will also trigger a warning. On return `*len` is set to the length of the scanned string, and `*flags` gives output flags.

If the value is  $\leq$  UV\_MAX it is returned as a UV, the output flags are clear, and nothing is written to `*result`. If the value is  $>$  UV\_MAX `grok_oct` returns UV\_MAX, sets PERL\_SCAN\_GREATER\_THAN\_UV\_MAX in the output flags, and writes the value to `*result` (or the value is discarded if `result` is NULL).

If PERL\_SCAN\_ALLOW\_UNDERSCORES is set in `*flags` then the octal number may use '\_' characters to separate digits.

```
UV grok_oct(char* start, STRLEN* len_p, I32* flags, NV *result)
```

#### scan\_bin

For backwards compatibility. Use `grok_bin` instead.

```
NV scan_bin(char* start, STRLEN len, STRLEN* retlen)
```

#### scan\_hex

For backwards compatibility. Use `grok_hex` instead.

```
NV scan_hex(char* start, STRLEN len, STRLEN* retlen)
```

#### scan\_oct

For backwards compatibility. Use `grok_oct` instead.

```
NV scan_oct(char* start, STRLEN len, STRLEN* retlen)
```

## Optree Manipulation Functions

#### cv\_const\_sv

If `cv` is a constant sub eligible for inlining, returns the constant value returned by the sub. Otherwise, returns NULL.

Constant subs can be created with `newCONSTSUB` or as described in "*Constant Functions*" in *perlsyn*.

```
SV* cv_const_sv(CV* cv)
```

**newCONSTSUB**

Creates a constant sub equivalent to Perl `sub FOO () { 123 }` which is eligible for inlining at compile-time.

```
CV* newCONSTSUB(HV* stash, char* name, SV* sv)
```

**newXS**

Used by `xsubpp` to hook up XSUBs as Perl subs.

**Pad Data Structures****pad\_sv**

Get the value at offset `po` in the current pad. Use macro `PAD_SV` instead of calling this function directly.

```
SV* pad_sv(PADOFFSET po)
```

**Stack Manipulation Macros****dMARK**

Declare a stack marker variable, `mark`, for the XSUB. See `MARK` and `dORIGMARK`.

```
dMARK;
```

**dORIGMARK**

Saves the original stack mark for the XSUB. See `ORIGMARK`.

```
dORIGMARK;
```

**dSP**

Declares a local copy of perl's stack pointer for the XSUB, available via the `SP` macro. See `SP`.

```
dSP;
```

**EXTEND**

Used to extend the argument stack for an XSUB's return values. Once used, guarantees that there is room for at least `nitems` to be pushed onto the stack.

```
void EXTEND(SP, int nitems)
```

**MARK**

Stack marker variable for the XSUB. See `dMARK`.

**mPUSHi**

Push an integer onto the stack. The stack must have room for this element. Handles 'set' magic. Does not use `TARG`. See also `PUSHi`, `mXPUSHi` and `XPUSHi`.

```
void mPUSHi(IV iv)
```

**mPUSHn**

Push a double onto the stack. The stack must have room for this element. Handles 'set' magic. Does not use `TARG`. See also `PUSHn`, `mXPUSHn` and `XPUSHn`.

```
void mPUSHn(NV nv)
```

**mPUSHp**

Push a string onto the stack. The stack must have room for this element. The `len` indicates the length of the string. Handles 'set' magic. Does not use `TARG`. See also `PUSHp`, `mXPUSHp` and `XPUSHp`.

```
void mPUSHp(char* str, STRLEN len)
```

#### mPUSHu

Push an unsigned integer onto the stack. The stack must have room for this element. Handles 'set' magic. Does not use `TARG`. See also `PUSHu`, `mXPUSHu` and `XPUSHu`.

```
void mPUSHu(UV uv)
```

#### mXPUSHi

Push an integer onto the stack, extending the stack if necessary. Handles 'set' magic. Does not use `TARG`. See also `XPUSHi`, `mPUSHi` and `PUSHi`.

```
void mXPUSHi(IV iv)
```

#### mXPUSHn

Push a double onto the stack, extending the stack if necessary. Handles 'set' magic. Does not use `TARG`. See also `XPUSHn`, `mPUSHn` and `PUSHn`.

```
void mXPUSHn(NV nv)
```

#### mXPUSHp

Push a string onto the stack, extending the stack if necessary. The `len` indicates the length of the string. Handles 'set' magic. Does not use `TARG`. See also `XPUSHp`, `mPUSHp` and `PUSHp`.

```
void mXPUSHp(char* str, STRLEN len)
```

#### mXPUSHu

Push an unsigned integer onto the stack, extending the stack if necessary. Handles 'set' magic. Does not use `TARG`. See also `XPUSHu`, `mPUSHu` and `PUSHu`.

```
void mXPUSHu(UV uv)
```

#### ORIGMARK

The original stack mark for the `XSUB`. See `dORIGMARK`.

#### POPi

Pops an integer off the stack.

```
IV POPi
```

#### POPi

Pops a long off the stack.

```
long POPl
```

#### POPn

Pops a double off the stack.

```
NV POPn
```

#### POPp

Pops a string off the stack. Deprecated. New code should use POPpx.

```
char* POPp
```

#### POPpbytex

Pops a string off the stack which must consist of bytes i.e. characters < 256.

```
char* POPpbytex
```

#### POPpx

Pops a string off the stack.

```
char* POPpx
```

#### POPs

Pops an SV off the stack.

```
SV* POPs
```

#### PUSHi

Push an integer onto the stack. The stack must have room for this element. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mPUSHi instead. See also XPUSHi and mXPUSHi.

```
void PUSHi(IV iv)
```

#### PUSHMARK

Opening bracket for arguments on a callback. See PUTBACK and *percall*.

```
void PUSHMARK(SP)
```

#### PUSHmortal

Push a new mortal SV onto the stack. The stack must have room for this element. Does not handle 'set' magic. Does not use TARG. See also PUSHs, XPUSHmortal and XPUSHs.

```
void PUSHmortal()
```

#### PUSHn

Push a double onto the stack. The stack must have room for this element. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mPUSHn instead. See also XPUSHn and mXPUSHn.

```
void PUSHn(NV nv)
```

#### PUSHp

Push a string onto the stack. The stack must have room for this element. The len indicates the length of the string. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mPUSHp instead. See also XPUSHp and mXPUSHp.

```
void PUSHp(char* str, STRLEN len)
```

#### PUSHs



Push an SV onto the stack. The stack must have room for this element. Does not handle 'set' magic. Does not use TARG. See also PUSHmortal, XPUSHs and XPUSHmortal.

```
void PUSHs(SV* sv)
```

#### PUSHu

Push an unsigned integer onto the stack. The stack must have room for this element. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mPUSHu instead. See also XPUSHu and mXPUSHu.

```
void PUSHu(UV uv)
```

#### PUTBACK

Closing bracket for XSUB arguments. This is usually handled by xsubpp. See PUSHMARK and *percall* for other uses.

```
PUTBACK;
```

#### SP

Stack pointer. This is usually handled by xsubpp. See dSP and SPAGAIN.

#### SPAGAIN

Refetch the stack pointer. Used after a callback. See *percall*.

```
SPAGAIN;
```

#### XPUSHi

Push an integer onto the stack, extending the stack if necessary. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mXPUSHi instead. See also PUSHi and mPUSHi.

```
void XPUSHi(IV iv)
```

#### XPUSHmortal

Push a new mortal SV onto the stack, extending the stack if necessary. Does not handle 'set' magic. Does not use TARG. See also XPUSHs, PUSHmortal and PUSHs.

```
void XPUSHmortal()
```

#### XPUSHn

Push a double onto the stack, extending the stack if necessary. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mXPUSHn instead. See also PUSHn and mPUSHn.

```
void XPUSHn(NV nv)
```

#### XPUSHp

Push a string onto the stack, extending the stack if necessary. The len indicates the length of the string. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mXPUSHp instead. See also PUSHp and mPUSHp.

```
void XPUSHp(char* str, STRLEN len)
```

**XPUSHs**

Push an SV onto the stack, extending the stack if necessary. Does not handle 'set' magic. Does not use TARG. See also XPUSHmortal, PUSHs and PUSHmortal.

```
void XPUSHs(SV* sv)
```

**XPUSHu**

Push an unsigned integer onto the stack, extending the stack if necessary. Handles 'set' magic. Uses TARG, so dTARGET or dXSTARG should be called to declare it. Do not call multiple TARG-oriented macros to return lists from XSUB's - see mXPUSHu instead. See also PUSHu and mPUSHu.

```
void XPUSHu(UV uv)
```

**XSRETURN**

Return from XSUB, indicating number of items on the stack. This is usually handled by xsubpp.

```
void XSRETURN(int nitems)
```

**XSRETURN\_EMPTY**

Return an empty list from an XSUB immediately.

```
XSRETURN_EMPTY;
```

**XSRETURN\_IV**

Return an integer from an XSUB immediately. Uses XST\_mIV.

```
void XSRETURN_IV(IV iv)
```

**XSRETURN\_NO**

Return &PL\_sv\_no from an XSUB immediately. Uses XST\_mNO.

```
XSRETURN_NO;
```

**XSRETURN\_NV**

Return a double from an XSUB immediately. Uses XST\_mNV.

```
void XSRETURN_NV(NV nv)
```

**XSRETURN\_PV**

Return a copy of a string from an XSUB immediately. Uses XST\_mPV.

```
void XSRETURN_PV(char* str)
```

**XSRETURN\_UNDEF**

Return &PL\_sv\_undef from an XSUB immediately. Uses XST\_mUNDEF.

```
XSRETURN_UNDEF;
```

**XSRETURN\_UV**

Return an integer from an XSUB immediately. Uses XST\_mUV.

```
void XSRETURN_UV(IV uv)
```

**XSRETURN\_YES**

Return `&PL_sv_yes` from an XSUB immediately. Uses `XST_mYES`.

```
XSRETURN_YES;
```

#### XST\_mIV

Place an integer into the specified position `pos` on the stack. The value is stored in a new mortal SV.

```
void XST_mIV(int pos, IV iv)
```

#### XST\_mNO

Place `&PL_sv_no` into the specified position `pos` on the stack.

```
void XST_mNO(int pos)
```

#### XST\_mNV

Place a double into the specified position `pos` on the stack. The value is stored in a new mortal SV.

```
void XST_mNV(int pos, NV nv)
```

#### XST\_mPV

Place a copy of a string into the specified position `pos` on the stack. The value is stored in a new mortal SV.

```
void XST_mPV(int pos, char* str)
```

#### XST\_mUNDEF

Place `&PL_sv_undef` into the specified position `pos` on the stack.

```
void XST_mUNDEF(int pos)
```

#### XST\_mYES

Place `&PL_sv_yes` into the specified position `pos` on the stack.

```
void XST_mYES(int pos)
```

## SV Flags

#### svtype

An enum of flags for Perl types. These are found in the file `sv.h` in the `svtype` enum. Test these flags with the `SVTYPE` macro.

#### SVt\_IV

Integer type flag for scalars. See `svtype`.

#### SVt\_NV

Double type flag for scalars. See `svtype`.

#### SVt\_PV

Pointer type flag for scalars. See `svtype`.

#### SVt\_PVAV

Type flag for arrays. See `svtype`.

#### SVt\_PVCV

Type flag for code refs. See `svtype`.

SVt\_PVHV

Type flag for hashes. See `svtype`.

SVt\_PVMG

Type flag for blessed scalars. See `svtype`.

## SV Manipulation Functions

`get_sv`

Returns the SV of the specified Perl scalar. If `create` is set and the Perl variable does not exist then it will be created. If `create` is not set and the variable does not exist then NULL is returned.

NOTE: the `perl_` form of this function is deprecated.

```
SV* get_sv(const char* name, I32 create)
```

`looks_like_number`

Test if the content of an SV looks like a number (or is a number). `Inf` and `Infinity` are treated as numbers (so will not issue a non-numeric warning), even if your `atof()` doesn't grok them.

```
I32 looks_like_number(SV* sv)
```

`newRV_inc`

Creates an RV wrapper for an SV. The reference count for the original SV is incremented.

```
SV* newRV_inc(SV* sv)
```

`newRV_noinc`

Creates an RV wrapper for an SV. The reference count for the original SV is **not** incremented.

```
SV* newRV_noinc(SV *sv)
```

`NEWSV`

Creates a new SV. A non-zero `len` parameter indicates the number of bytes of preallocated string space the SV should have. An extra byte for a trailing NUL is also reserved. (SvPOK is not set for the SV even if string space is allocated.) The reference count for the new SV is set to 1. `id` is an integer id between 0 and 1299 (used to identify leaks).

```
SV* NEWSV(int id, STRLEN len)
```

`newSV`

Create a new null SV, or if `len > 0`, create a new empty SVt\_PV type SV with an initial PV allocation of `len+1`. Normally accessed via the `NEWSV` macro.

```
SV* newSV(STRLEN len)
```

`newSVhek`

Creates a new SV from the hash key structure. It will generate scalars that point to the shared string table where possible. Returns a new (undefined) SV if the `hek` is NULL.

```
SV* newSVhek(const HEK *hek)
```

**newSViv**

Creates a new SV and copies an integer into it. The reference count for the SV is set to 1.

```
SV* newSViv(IV i)
```

**newSVnv**

Creates a new SV and copies a floating point value into it. The reference count for the SV is set to 1.

```
SV* newSVnv(NV n)
```

**newSVpv**

Creates a new SV and copies a string into it. The reference count for the SV is set to 1. If `len` is zero, Perl will compute the length using `strlen()`. For efficiency, consider using `newSVpvn` instead.

```
SV* newSVpv(const char* s, STRLEN len)
```

**newSVpvf**

Creates a new SV and initializes it with the string formatted like `sprintf`.

```
SV* newSVpvf(const char* pat, ...)
```

**newSVpvn**

Creates a new SV and copies a string into it. The reference count for the SV is set to 1. Note that if `len` is zero, Perl will create a zero length string. You are responsible for ensuring that the source string is at least `len` bytes long. If the `s` argument is NULL the new SV will be undefined.

```
SV* newSVpvn(const char* s, STRLEN len)
```

**newSVpvn\_share**

Creates a new SV with its `SvPVX_const` pointing to a shared string in the string table. If the string does not already exist in the table, it is created first. Turns on `READONLY` and `FAKE`. The string's hash is stored in the UV slot of the SV; if the `hash` parameter is non-zero, that value is used; otherwise the hash is computed. The idea here is that as the string table is used for shared hash keys these strings will have `SvPVX_const == HeKEY` and hash lookup will avoid string compare.

```
SV* newSVpvn_share(const char* s, I32 len, U32 hash)
```

**newSVrv**

Creates a new SV for the RV, `rv`, to point to. If `rv` is not an RV then it will be upgraded to one. If `classname` is non-null then the new SV will be blessed in the specified package. The new SV is returned and its reference count is 1.

```
SV* newSVrv(SV* rv, const char* classname)
```

**newSVsv**

Creates a new SV which is an exact duplicate of the original SV. (Uses `sv_setsv`).

```
SV* newSVsv(SV* old)
```

**newSVuv**

Creates a new SV and copies an unsigned integer into it. The reference count for the

SV is set to 1.

```
SV* newSVuv(UV u)
```

### SvCUR

Returns the length of the string which is in the SV. See SvLEN.

```
STRLEN SvCUR(SV* sv)
```

### SvCUR\_set

Set the current length of the string which is in the SV. See SvCUR and SvIV\_set.

```
void SvCUR_set(SV* sv, STRLEN len)
```

### SvEND

Returns a pointer to the last character in the string which is in the SV. See SvCUR. Access the character as `*(SvEND(sv))`.

```
char* SvEND(SV* sv)
```

### SvGROW

Expands the character buffer in the SV so that it has room for the indicated number of bytes (remember to reserve space for an extra trailing NUL character). Calls `sv_grow` to perform the expansion if necessary. Returns a pointer to the character buffer.

```
char * SvGROW(SV* sv, STRLEN len)
```

### SvIOK

Returns a boolean indicating whether the SV contains an integer.

```
bool SvIOK(SV* sv)
```

### SvIOKp

Returns a boolean indicating whether the SV contains an integer. Checks the **private** setting. Use SvIOK.

```
bool SvIOKp(SV* sv)
```

### SvIOK\_notUV

Returns a boolean indicating whether the SV contains a signed integer.

```
bool SvIOK_notUV(SV* sv)
```

### SvIOK\_off

Unsets the IV status of an SV.

```
void SvIOK_off(SV* sv)
```

### SvIOK\_on

Tells an SV that it is an integer.

```
void SvIOK_on(SV* sv)
```

### SvIOK\_only

Tells an SV that it is an integer and disables all other OK bits.

```
void SvIOK_only(SV* sv)
```

**SvIOK\_only\_UV**

Tells and SV that it is an unsigned integer and disables all other OK bits.

```
void SvIOK_only_UV(SV* sv)
```

**SvIOK\_UV**

Returns a boolean indicating whether the SV contains an unsigned integer.

```
bool SvIOK_UV(SV* sv)
```

**SvIsCOW**

Returns a boolean indicating whether the SV is Copy-On-Write. (either shared hash key scalars, or full Copy On Write scalars if 5.9.0 is configured for COW)

```
bool SvIsCOW(SV* sv)
```

**SvIsCOW\_shared\_hash**

Returns a boolean indicating whether the SV is Copy-On-Write shared hash key scalar.

```
bool SvIsCOW_shared_hash(SV* sv)
```

**SvIV**

Coerces the given SV to an integer and returns it. See `SvIVx` for a version which guarantees to evaluate `sv` only once.

```
IV SvIV(SV* sv)
```

**SvIVX**

Returns the raw value in the SV's IV slot, without checks or conversions. Only use when you are sure `SvIOK` is true. See also `SvIV()`.

```
IV SvIVX(SV* sv)
```

**SvIVx**

Coerces the given SV to an integer and returns it. Guarantees to evaluate `sv` only once. Use the more efficient `SvIV` otherwise.

```
IV SvIVx(SV* sv)
```

**SvIV\_set**

Set the value of the IV pointer in `sv` to `val`. It is possible to perform the same function of this macro with an lvalue assignment to `SvIVX`. With future Perls, however, it will be more efficient to use `SvIV_set` instead of the lvalue assignment to `SvIVX`.

```
void SvIV_set(SV* sv, IV val)
```

**SvLEN**

Returns the size of the string buffer in the SV, not including any part attributable to `SvOOK`. See `SvCUR`.

```
STRLEN SvLEN(SV* sv)
```

**SvLEN\_set**

Set the actual length of the string which is in the SV. See `SvIV_set`.

```
void SvLEN_set(SV* sv, STRLEN len)
```

#### SvMAGIC\_set

Set the value of the MAGIC pointer in sv to val. See SvIV\_set.

```
void SvMAGIC_set(SV* sv, MAGIC* val)
```

#### SvNIOK

Returns a boolean indicating whether the SV contains a number, integer or double.

```
bool SvNIOK(SV* sv)
```

#### SvNIOKp

Returns a boolean indicating whether the SV contains a number, integer or double. Checks the **private** setting. Use SvNIOK.

```
bool SvNIOKp(SV* sv)
```

#### SvNIOK\_off

Unsets the NV/IV status of an SV.

```
void SvNIOK_off(SV* sv)
```

#### SvNOK

Returns a boolean indicating whether the SV contains a double.

```
bool SvNOK(SV* sv)
```

#### SvNOKp

Returns a boolean indicating whether the SV contains a double. Checks the **private** setting. Use SvNOK.

```
bool SvNOKp(SV* sv)
```

#### SvNOK\_off

Unsets the NV status of an SV.

```
void SvNOK_off(SV* sv)
```

#### SvNOK\_on

Tells an SV that it is a double.

```
void SvNOK_on(SV* sv)
```

#### SvNOK\_only

Tells an SV that it is a double and disables all other OK bits.

```
void SvNOK_only(SV* sv)
```

#### SvNV

Coerce the given SV to a double and return it. See SvNVx for a version which guarantees to evaluate sv only once.

```
NV SvNV(SV* sv)
```

#### SvNVX



Returns the raw value in the SV's NV slot, without checks or conversions. Only use when you are sure SvNOK is true. See also SvNV( ).

```
NV SvNVX(SV* sv)
```

#### SvNVx

Coerces the given SV to a double and returns it. Guarantees to evaluate sv only once. Use the more efficient SvNV otherwise.

```
NV SvNVx(SV* sv)
```

#### SvNV\_set

Set the value of the NV pointer in sv to val. See SvIV\_set.

```
void SvNV_set(SV* sv, NV val)
```

#### SvOK

Returns a boolean indicating whether the value is an SV. It also tells whether the value is defined or not.

```
bool SvOK(SV* sv)
```

#### SvOOK

Returns a boolean indicating whether the SvIVX is a valid offset value for the SvPVX. This hack is used internally to speed up removal of characters from the beginning of a SvPV. When SvOOK is true, then the start of the allocated string buffer is really (SvPVX - SvIVX).

```
bool SvOOK(SV* sv)
```

#### SvPOK

Returns a boolean indicating whether the SV contains a character string.

```
bool SvPOK(SV* sv)
```

#### SvPOKp

Returns a boolean indicating whether the SV contains a character string. Checks the **private** setting. Use SvPOK.

```
bool SvPOKp(SV* sv)
```

#### SvPOK\_off

Unsets the PV status of an SV.

```
void SvPOK_off(SV* sv)
```

#### SvPOK\_on

Tells an SV that it is a string.

```
void SvPOK_on(SV* sv)
```

#### SvPOK\_only

Tells an SV that it is a string and disables all other OK bits. Will also turn off the UTF-8 status.

```
void SvPOK_only(SV* sv)
```

### SvPOK\_only\_UTF8

Tells an SV that it is a string and disables all other OK bits, and leaves the UTF-8 status as it was.

```
void SvPOK_only_UTF8(SV* sv)
```

### SvPV

Returns a pointer to the string in the SV, or a stringified form of the SV if the SV does not contain a string. The SV may cache the stringified version becoming SvPOK. Handles 'get' magic. See also SvPVx for a version which guarantees to evaluate sv only once.

```
char* SvPV(SV* sv, STRLEN len)
```

### SvPVbyte

Like SvPV, but converts sv to byte representation first if necessary.

```
char* SvPVbyte(SV* sv, STRLEN len)
```

### SvPVbytex

Like SvPV, but converts sv to byte representation first if necessary. Guarantees to evaluate sv only once; use the more efficient SvPVbyte otherwise.

```
char* SvPVbytex(SV* sv, STRLEN len)
```

### SvPVbytex\_force

Like SvPV\_force, but converts sv to byte representation first if necessary. Guarantees to evaluate sv only once; use the more efficient SvPVbyte\_force otherwise.

```
char* SvPVbytex_force(SV* sv, STRLEN len)
```

### SvPVbyte\_force

Like SvPV\_force, but converts sv to byte representation first if necessary.

```
char* SvPVbyte_force(SV* sv, STRLEN len)
```

### SvPVbyte\_nolen

Like SvPV\_nolen, but converts sv to byte representation first if necessary.

```
char* SvPVbyte_nolen(SV* sv)
```

### SvPVutf8

Like SvPV, but converts sv to utf8 first if necessary.

```
char* SvPVutf8(SV* sv, STRLEN len)
```

### SvPVutf8x

Like SvPV, but converts sv to utf8 first if necessary. Guarantees to evaluate sv only once; use the more efficient SvPVutf8 otherwise.

```
char* SvPVutf8x(SV* sv, STRLEN len)
```

### SvPVutf8x\_force

Like SvPV\_force, but converts sv to utf8 first if necessary. Guarantees to evaluate sv only once; use the more efficient SvPVutf8\_force otherwise.

```
char* SvPVutf8x_force(SV* sv, STRLEN len)
```

#### SvPVutf8\_force

Like `SvPV_force`, but converts `sv` to utf8 first if necessary.

```
char* SvPVutf8_force(SV* sv, STRLEN len)
```

#### SvPVutf8\_nolen

Like `SvPV_nolen`, but converts `sv` to utf8 first if necessary.

```
char* SvPVutf8_nolen(SV* sv)
```

#### SvPVX

Returns a pointer to the physical string in the SV. The SV must contain a string.

```
char* SvPVX(SV* sv)
```

#### SvPVx

A version of `SvPV` which guarantees to evaluate `sv` only once.

```
char* SvPVx(SV* sv, STRLEN len)
```

#### SvPV\_force

Like `SvPV` but will force the SV into containing just a string (`SvPOK_only`). You want force if you are going to update the `SvPVX` directly.

```
char* SvPV_force(SV* sv, STRLEN len)
```

#### SvPV\_force\_nomg

Like `SvPV` but will force the SV into containing just a string (`SvPOK_only`). You want force if you are going to update the `SvPVX` directly. Doesn't process magic.

```
char* SvPV_force_nomg(SV* sv, STRLEN len)
```

#### SvPV\_nolen

Returns a pointer to the string in the SV, or a stringified form of the SV if the SV does not contain a string. The SV may cache the stringified form becoming `SvPOK`. Handles 'get' magic.

```
char* SvPV_nolen(SV* sv)
```

#### SvPV\_set

Set the value of the PV pointer in `sv` to `val`. See `SvIV_set`.

```
void SvPV_set(SV* sv, char* val)
```

#### SvREFCNT

Returns the value of the object's reference count.

```
U32 SvREFCNT(SV* sv)
```

#### SvREFCNT\_dec

Decrements the reference count of the given SV.

```
void SvREFCNT_dec(SV* sv)
```

**SvREFCNT\_inc**

Increments the reference count of the given SV.

```
SV* SvREFCNT_inc(SV* sv)
```

**SvROK**

Tests if the SV is an RV.

```
bool SvROK(SV* sv)
```

**SvROK\_off**

Unsets the RV status of an SV.

```
void SvROK_off(SV* sv)
```

**SvROK\_on**

Tells an SV that it is an RV.

```
void SvROK_on(SV* sv)
```

**SvRV**

Dereferences an RV to return the SV.

```
SV* SvRV(SV* sv)
```

**SvRV\_set**

Set the value of the RV pointer in sv to val. See `SvIV_set`.

```
void SvRV_set(SV* sv, SV* val)
```

**SvSTASH**

Returns the stash of the SV.

```
HV* SvSTASH(SV* sv)
```

**SvSTASH\_set**

Set the value of the STASH pointer in sv to val. See `SvIV_set`.

```
void SvSTASH_set(SV* sv, STASH* val)
```

**SvTAINT**

Taints an SV if tainting is enabled.

```
void SvTAINT(SV* sv)
```

**SvTAINTED**

Checks to see if an SV is tainted. Returns TRUE if it is, FALSE if not.

```
bool SvTAINTED(SV* sv)
```

**SvTAINTED\_off**

Untaints an SV. Be *very* careful with this routine, as it short-circuits some of Perl's fundamental security features. XS module authors should not use this function unless they fully understand all the implications of unconditionally untainting the value. Untainting should be done in the standard perl fashion, via a carefully crafted regexp, rather than directly untainting variables.

```
void SvTAINTED_off(SV* sv)
```

#### SvTAINTED\_on

Marks an SV as tainted if tainting is enabled.

```
void SvTAINTED_on(SV* sv)
```

#### SvTRUE

Returns a boolean indicating whether Perl would evaluate the SV as true or false, defined or undefined. Does not handle 'get' magic.

```
bool SvTRUE(SV* sv)
```

#### SvTYPE

Returns the type of the SV. See `svtype`.

```
svtype SvTYPE(SV* sv)
```

#### SvUOK

Returns a boolean indicating whether the SV contains an unsigned integer.

```
void SvUOK(SV* sv)
```

#### SvUPGRADE

Used to upgrade an SV to a more complex form. Uses `sv_upgrade` to perform the upgrade if necessary. See `svtype`.

```
void SvUPGRADE(SV* sv, svtype type)
```

#### SvUTF8

Returns a boolean indicating whether the SV contains UTF-8 encoded data.

```
bool SvUTF8(SV* sv)
```

#### SvUTF8\_off

Unsets the UTF-8 status of an SV.

```
void SvUTF8_off(SV *sv)
```

#### SvUTF8\_on

Turn on the UTF-8 status of an SV (the data is not changed, just the flag). Do not use frivolously.

```
void SvUTF8_on(SV *sv)
```

#### SvUV

Coerces the given SV to an unsigned integer and returns it. See `SvUVx` for a version which guarantees to evaluate `sv` only once.

```
UV SvUV(SV* sv)
```

#### SvUVX

Returns the raw value in the SV's UV slot, without checks or conversions. Only use when you are sure `SvIOK` is true. See also `SvUV()`.

```
UV SvUVX(SV* sv)
```

**SvUVx**

Coerces the given SV to an unsigned integer and returns it. Guarantees to evaluate `sv` only once. Use the more efficient `SvUV` otherwise.

```
UV SvUVx(SV* sv)
```

**SvUV\_set**

Set the value of the UV pointer in `sv` to `val`. See `SvIV_set`.

```
void SvUV_set(SV* sv, UV val)
```

**sv\_2bool**

This function is only called on magical items, and is only used by `sv_true()` or its macro equivalent.

```
bool sv_2bool(SV* sv)
```

**sv\_2cv**

Using various gambits, try to get a CV from an SV; in addition, try if possible to set `*st` and `*gvp` to the stash and GV associated with it.

```
CV* sv_2cv(SV* sv, HV** st, GV** gvp, I32 lref)
```

**sv\_2io**

Using various gambits, try to get an IO from an SV: the IO slot if its a GV; or the recursive result if we're an RV; or the IO slot of the symbol named after the PV if we're a string.

```
IO* sv_2io(SV* sv)
```

**sv\_2iv**

Return the integer value of an SV, doing any necessary string conversion, magic etc. Normally used via the `SvIV(sv)` and `SvIVx(sv)` macros.

```
IV sv_2iv(SV* sv)
```

**sv\_2mortal**

Marks an existing SV as mortal. The SV will be destroyed "soon", either by an explicit call to `FREETMPS`, or by an implicit call at places such as statement boundaries. `SvTEMP()` is turned on which means that the SV's string buffer can be "stolen" if this SV is copied. See also `sv_newmortal` and `sv_mortalcopy`.

```
SV* sv_2mortal(SV* sv)
```

**sv\_2nv**

Return the num value of an SV, doing any necessary string or integer conversion, magic etc. Normally used via the `SvNV(sv)` and `SvNVx(sv)` macros.

```
NV sv_2nv(SV* sv)
```

**sv\_2pvbyte**

Return a pointer to the byte-encoded representation of the SV, and set `*lp` to its length. May cause the SV to be downgraded from UTF-8 as a side-effect.

Usually accessed via the `SvPVbyte` macro.

```
char* sv_2pvbyte(SV* sv, STRLEN* lp)
```

**sv\_2pvbyte\_nolen**

Return a pointer to the byte-encoded representation of the SV. May cause the SV to be downgraded from UTF-8 as a side-effect.

Usually accessed via the `SvPVbyte_nolen` macro.

```
char* sv_2pvbyte_nolen(SV* sv)
```

**sv\_2pvutf8**

Return a pointer to the UTF-8-encoded representation of the SV, and set `*lp` to its length. May cause the SV to be upgraded to UTF-8 as a side-effect.

Usually accessed via the `SvPVutf8` macro.

```
char* sv_2pvutf8(SV* sv, STRLEN* lp)
```

**sv\_2pvutf8\_nolen**

Return a pointer to the UTF-8-encoded representation of the SV. May cause the SV to be upgraded to UTF-8 as a side-effect.

Usually accessed via the `SvPVutf8_nolen` macro.

```
char* sv_2pvutf8_nolen(SV* sv)
```

**sv\_2pv\_flags**

Returns a pointer to the string value of an SV, and sets `*lp` to its length. If `flags` includes `SV_GMAGIC`, does an `mg_get()` first. Coerces `sv` to a string if necessary. Normally invoked via the `SvPV_flags` macro. `sv_2pv()` and `sv_2pv_nomg` usually end up here too.

```
char* sv_2pv_flags(SV* sv, STRLEN* lp, I32 flags)
```

**sv\_2pv\_nolen**

Like `sv_2pv()`, but doesn't return the length too. You should usually use the macro wrapper `SvPV_nolen(sv)` instead. `char* sv_2pv_nolen(SV* sv)`

**sv\_2uv**

Return the unsigned integer value of an SV, doing any necessary string conversion, magic etc. Normally used via the `SvUV(sv)` and `SvUVx(sv)` macros.

```
UV sv_2uv(SV* sv)
```

**sv\_backoff**

Remove any string offset. You should normally use the `SvOOK_off` macro wrapper instead.

```
int sv_backoff(SV* sv)
```

**sv\_bless**

Blesses an SV into a specified package. The SV must be an RV. The package must be designated by its stash (see `gv_stashpv()`). The reference count of the SV is unaffected.

```
SV* sv_bless(SV* sv, HV* stash)
```

**sv\_catpv**

Concatenates the string onto the end of the string which is in the SV. If the SV has the UTF-8 status set, then the bytes appended should be valid UTF-8. Handles 'get'

magic, but not 'set' magic. See `sv_catpv_mg`.

```
void sv_catpv(SV* sv, const char* ptr)
```

#### `sv_catpvf`

Processes its arguments like `sprintf` and appends the formatted output to an SV. If the appended data contains "wide" characters (including, but not limited to, SVs with a UTF-8 PV formatted with `%s`, and characters `>255` formatted with `%c`), the original SV might get upgraded to UTF-8. Handles 'get' magic, but not 'set' magic. See `sv_catpvf_mg`. If the original SV was UTF-8, the pattern should be valid UTF-8; if the original SV was bytes, the pattern should be too.

```
void sv_catpvf(SV* sv, const char* pat, ...)
```

#### `sv_catpvf_mg`

Like `sv_catpvf`, but also handles 'set' magic.

```
void sv_catpvf_mg(SV *sv, const char* pat, ...)
```

#### `sv_catpvn`

Concatenates the string onto the end of the string which is in the SV. The `len` indicates number of bytes to copy. If the SV has the UTF-8 status set, then the bytes appended should be valid UTF-8. Handles 'get' magic, but not 'set' magic. See `sv_catpvn_mg`.

```
void sv_catpvn(SV* sv, const char* ptr, STRLEN len)
```

#### `sv_catpvn_flags`

Concatenates the string onto the end of the string which is in the SV. The `len` indicates number of bytes to copy. If the SV has the UTF-8 status set, then the bytes appended should be valid UTF-8. If `flags` has `SV_GMAGIC` bit set, will `mg_get` on `dsv` if appropriate, else not. `sv_catpvn` and `sv_catpvn_nomg` are implemented in terms of this function.

```
void sv_catpvn_flags(SV* sv, const char* ptr, STRLEN len, I32 flags)
```

#### `sv_catpvn_mg`

Like `sv_catpvn`, but also handles 'set' magic.

```
void sv_catpvn_mg(SV *sv, const char *ptr, STRLEN len)
```

#### `sv_catpvn_nomg`

Like `sv_catpvn` but doesn't process magic.

```
void sv_catpvn_nomg(SV* sv, const char* ptr, STRLEN len)
```

#### `sv_catpv_mg`

Like `sv_catpv`, but also handles 'set' magic.

```
void sv_catpv_mg(SV *sv, const char *ptr)
```

#### `sv_catsv`

Concatenates the string from SV `ssv` onto the end of the string in SV `dsv`. Modifies `dsv` but not `ssv`. Handles 'get' magic, but not 'set' magic. See `sv_catsv_mg`.

```
void sv_catsv(SV* dsv, SV* ssv)
```



### sv\_catsv\_flags

Concatenates the string from SV *ssv* onto the end of the string in SV *dsv*. Modifies *dsv* but not *ssv*. If *flags* has `SV_GMAGIC` bit set, will `mg_get` on the SVs if appropriate, else not. `sv_catsv` and `sv_catsv_nomg` are implemented in terms of this function.

```
void sv_catsv_flags(SV* dsv, SV* ssv, I32 flags)
```

### sv\_catsv\_mg

Like `sv_catsv`, but also handles 'set' magic.

```
void sv_catsv_mg(SV *dstr, SV *sstr)
```

### sv\_catsv\_nomg

Like `sv_catsv` but doesn't process magic.

```
void sv_catsv_nomg(SV* dsv, SV* ssv)
```

### sv\_chop

Efficient removal of characters from the beginning of the string buffer. `SvPOK(sv)` must be true and the `ptr` must be a pointer to somewhere inside the string buffer. The `ptr` becomes the first character of the adjusted string. Uses the "OOK hack". Beware: after this function returns, `ptr` and `SvPVX_const(sv)` may no longer refer to the same chunk of data.

```
void sv_chop(SV* sv, char* ptr)
```

### sv\_clear

Clear an SV: call any destructors, free up any memory used by the body, and free the body itself. The SV's head is *not* freed, although its type is set to all 1's so that it won't inadvertently be assumed to be live during global destruction etc. This function should only be called when `REFCNT` is zero. Most of the time you'll want to call `sv_free()` (or its macro wrapper `SvREFCNT_dec`) instead.

```
void sv_clear(SV* sv)
```

### sv\_cmp

Compares the strings in two SVs. Returns -1, 0, or 1 indicating whether the string in *sv1* is less than, equal to, or greater than the string in *sv2*. Is UTF-8 and 'use bytes' aware, handles get magic, and will coerce its args to strings if necessary. See also `sv_cmp_locale`.

```
I32 sv_cmp(SV* sv1, SV* sv2)
```

### sv\_cmp\_locale

Compares the strings in two SVs in a locale-aware manner. Is UTF-8 and 'use bytes' aware, handles get magic, and will coerce its args to strings if necessary. See also `sv_cmp_locale`. See also `sv_cmp`.

```
I32 sv_cmp_locale(SV* sv1, SV* sv2)
```

### sv\_collxfrm

Add Collate Transform magic to an SV if it doesn't already have it.

Any scalar variable may carry `PERL_MAGIC_collxfrm` magic that contains the scalar data of the variable, but transformed to such a format that a normal memory

comparison can be used to compare the data according to the locale settings.

```
char* sv_collxfrm(SV* sv, STRLEN* nxp)
```

#### sv\_copypv

Copies a stringified representation of the source SV into the destination SV. Automatically performs any necessary mg\_get and coercion of numeric values into strings. Guaranteed to preserve UTF-8 flag even from overloaded objects. Similar in nature to sv\_2pv[\_flags] but operates directly on an SV instead of just the string. Mostly uses sv\_2pv\_flags to do its work, except when that would lose the UTF-8'ness of the PV.

```
void sv_copypv(SV* dsv, SV* ssv)
```

#### sv\_dec

Auto-decrement of the value in the SV, doing string to numeric conversion if necessary. Handles 'get' magic.

```
void sv_dec(SV* sv)
```

#### sv\_derived\_from

Returns a boolean indicating whether the SV is derived from the specified class. This is the function that implements UNIVERSAL::isa. It works for class names as well as for objects.

```
bool sv_derived_from(SV* sv, const char* name)
```

#### sv\_eq

Returns a boolean indicating whether the strings in the two SVs are identical. Is UTF-8 and 'use bytes' aware, handles get magic, and will coerce its args to strings if necessary.

```
I32 sv_eq(SV* sv1, SV* sv2)
```

#### sv\_force\_normal

Undo various types of fakery on an SV: if the PV is a shared string, make a private copy; if we're a ref, stop refing; if we're a glob, downgrade to an xpvmg. See also sv\_force\_normal\_flags.

```
void sv_force_normal(SV *sv)
```

#### sv\_force\_normal\_flags

Undo various types of fakery on an SV: if the PV is a shared string, make a private copy; if we're a ref, stop refing; if we're a glob, downgrade to an xpvmg. The flags parameter gets passed to sv\_unref\_flags() when unrefing. sv\_force\_normal calls this function with flags set to 0.

```
void sv_force_normal_flags(SV *sv, U32 flags)
```

#### sv\_free

Decrement an SV's reference count, and if it drops to zero, call sv\_clear to invoke destructors and free up any memory used by the body; finally, deallocate the SV's head itself. Normally called via a wrapper macro SvREFCNT\_dec.

```
void sv_free(SV* sv)
```

**sv\_gets**

Get a line from the filehandle and store it into the SV, optionally appending to the currently-stored string.

```
char* sv_gets(SV* sv, PerlIO* fp, I32 append)
```

**sv\_grow**

Expands the character buffer in the SV. If necessary, uses `sv_unref` and upgrades the SV to `SVt_PV`. Returns a pointer to the character buffer. Use the `sv_grow` wrapper instead.

```
char* sv_grow(SV* sv, STRLEN newlen)
```

**sv\_inc**

Auto-increment of the value in the SV, doing string to numeric conversion if necessary. Handles 'get' magic.

```
void sv_inc(SV* sv)
```

**sv\_insert**

Inserts a string at the specified offset/length within the SV. Similar to the Perl `substr()` function.

```
void sv_insert(SV* bigsv, STRLEN offset, STRLEN len, char* little, STRLEN littlelen)
```

**sv\_isa**

Returns a boolean indicating whether the SV is blessed into the specified class. This does not check for subtypes; use `sv_derived_from` to verify an inheritance relationship.

```
int sv_isa(SV* sv, const char* name)
```

**sv\_isobject**

Returns a boolean indicating whether the SV is an RV pointing to a blessed object. If the SV is not an RV, or if the object is not blessed, then this will return false.

```
int sv_isobject(SV* sv)
```

**sv\_iv**

A private implementation of the `svIVx` macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
IV sv_iv(SV* sv)
```

**sv\_len**

Returns the length of the string in the SV. Handles magic and type coercion. See also `svCUR`, which gives raw access to the `xpv_cur` slot.

```
STRLEN sv_len(SV* sv)
```

**sv\_len\_utf8**

Returns the number of characters in the string in an SV, counting wide UTF-8 bytes as a single character. Handles magic and type coercion.

```
STRLEN sv_len_utf8(SV* sv)
```

### sv\_magic

Adds magic to an SV. First upgrades `sv` to type `SVt_PVMG` if necessary, then adds a new magic item of type `how` to the head of the magic list.

See `sv_magicext` (which `sv_magic` now calls) for a description of the handling of the `name` and `namlen` arguments.

You need to use `sv_magicext` to add magic to `SvREADONLY` SVs and also to add more than one instance of the same 'how'.

```
void sv_magic(SV* sv, SV* obj, int how, const char* name, I32 namlen)
```

### sv\_magicext

Adds magic to an SV, upgrading it if necessary. Applies the supplied vtable and returns a pointer to the magic added.

Note that `sv_magicext` will allow things that `sv_magic` will not. In particular, you can add magic to `SvREADONLY` SVs, and add more than one instance of the same 'how'.

If `namlen` is greater than zero then a `savepv` copy of `name` is stored, if `namlen` is zero then `name` is stored as-is and - as another special case - if `(name && namlen == HEf_SVKEY)` then `name` is assumed to contain an `SV*` and is stored as-is with its `REFCNT` incremented.

(This is now used as a subroutine by `sv_magic`.)

```
MAGIC * sv_magicext(SV* sv, SV* obj, int how, MGVTBL *vtbl, const char* name, I32 namlen)
```

### sv\_mortalcopy

Creates a new SV which is a copy of the original SV (using `sv_setsv`). The new SV is marked as mortal. It will be destroyed "soon", either by an explicit call to `FREETMPS`, or by an implicit call at places such as statement boundaries. See also `sv_newmortal` and `sv_2mortal`.

```
SV* sv_mortalcopy(SV* oldsv)
```

### sv\_newmortal

Creates a new null SV which is mortal. The reference count of the SV is set to 1. It will be destroyed "soon", either by an explicit call to `FREETMPS`, or by an implicit call at places such as statement boundaries. See also `sv_mortalcopy` and `sv_2mortal`.

```
SV* sv_newmortal()
```

### sv\_newref

Increment an SV's reference count. Use the `SvREFCNT_inc()` wrapper instead.

```
SV* sv_newref(SV* sv)
```

### sv\_nv

A private implementation of the `SvNVx` macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
NV sv_nv(SV* sv)
```

### sv\_pos\_b2u

Converts the value pointed to by `offsetp` from a count of bytes from the start of the string, to a count of the equivalent number of UTF-8 chars. Handles magic and type

coercion. void sv\_pos\_b2u(SV\* sv, I32\* offsetp)

#### sv\_pos\_u2b

Converts the value pointed to by offsetp from a count of UTF-8 chars from the start of the string, to a count of the equivalent number of bytes; if lenp is non-zero, it does the same to lenp, but this time starting from the offset, rather than from the start of the string. Handles magic and type coercion.

```
void sv_pos_u2b(SV* sv, I32* offsetp, I32* lenp)
```

#### sv\_pv

Use the SvPV\_nolen macro instead

```
char* sv_pv(SV *sv)
```

#### sv\_pvbyte

Use SvPVbyte\_nolen instead.

```
char* sv_pvbyte(SV *sv)
```

#### sv\_pvbyten

A private implementation of the SvPVbyte macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
char* sv_pvbyten(SV *sv, STRLEN *len)
```

#### sv\_pvbyten\_force

A private implementation of the SvPVbytex\_force macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
char* sv_pvbyten_force(SV* sv, STRLEN* lp)
```

#### sv\_pvn

A private implementation of the SvPV macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
char* sv_pvn(SV *sv, STRLEN *len)
```

#### sv\_pvn\_force

Get a sensible string out of the SV somehow. A private implementation of the SvPV\_force macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
char* sv_pvn_force(SV* sv, STRLEN* lp)
```

#### sv\_pvn\_force\_flags

Get a sensible string out of the SV somehow. If flags has SV\_GMAGIC bit set, will mg\_get on sv if appropriate, else not. sv\_pvn\_force and sv\_pvn\_force\_nomg are implemented in terms of this function. You normally want to use the various wrapper macros instead: see SvPV\_force and SvPV\_force\_nomg

```
char* sv_pvn_force_flags(SV* sv, STRLEN* lp, I32 flags)
```

#### sv\_pvutf8

Use the SvPVutf8\_nolen macro instead

```
char* sv_pvutf8(SV *sv)
```

#### sv\_pvutf8n

A private implementation of the `SvPVutf8` macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
char* sv_pvutf8n(SV *sv, STRLEN *len)
```

#### sv\_pvutf8n\_force

A private implementation of the `SvPVutf8_force` macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
char* sv_pvutf8n_force(SV* sv, STRLEN* lp)
```

#### sv\_reftype

Returns a string describing what the SV is a reference to.

```
char* sv_reftype(SV* sv, int ob)
```

#### sv\_replace

Make the first argument a copy of the second, then delete the original. The target SV physically takes over ownership of the body of the source SV and inherits its flags; however, the target keeps any magic it owns, and any magic in the source is discarded. Note that this is a rather specialist SV copying operation; most of the time you'll want to use `sv_setsv` or one of its many macro front-ends.

```
void sv_replace(SV* sv, SV* nsv)
```

#### sv\_report\_used

Dump the contents of all SVs not yet freed. (Debugging aid).

```
void sv_report_used()
```

#### sv\_reset

Underlying implementation for the `reset` Perl function. Note that the perl-level function is vaguely deprecated.

```
void sv_reset(char* s, HV* stash)
```

#### sv\_rvweaken

Weaken a reference: set the `SvWEAKREF` flag on this RV; give the referred-to SV `PERL_MAGIC_backref` magic if it hasn't already; and push a back-reference to this RV onto the array of backreferences associated with that magic.

```
SV* sv_rvweaken(SV *sv)
```

#### sv\_setiv

Copies an integer into the given SV, upgrading first if necessary. Does not handle 'set' magic. See also `sv_setiv_mg`.

```
void sv_setiv(SV* sv, IV num)
```

#### sv\_setiv\_mg

Like `sv_setiv`, but also handles 'set' magic.

```
void sv_setiv_mg(SV *sv, IV i)
```

**sv\_setnv**

Copies a double into the given SV, upgrading first if necessary. Does not handle 'set' magic. See also `sv_setnv_mg`.

```
void sv_setnv(SV* sv, NV num)
```

**sv\_setnv\_mg**

Like `sv_setnv`, but also handles 'set' magic.

```
void sv_setnv_mg(SV *sv, NV num)
```

**sv\_setpv**

Copies a string into an SV. The string must be null-terminated. Does not handle 'set' magic. See `sv_setpv_mg`.

```
void sv_setpv(SV* sv, const char* ptr)
```

**sv\_setpvf**

Works like `sv_catpvf` but copies the text into the SV instead of appending it. Does not handle 'set' magic. See `sv_setpvf_mg`.

```
void sv_setpvf(SV* sv, const char* pat, ...)
```

**sv\_setpvf\_mg**

Like `sv_setpvf`, but also handles 'set' magic.

```
void sv_setpvf_mg(SV *sv, const char* pat, ...)
```

**sv\_setpviv**

Copies an integer into the given SV, also updating its string value. Does not handle 'set' magic. See `sv_setpviv_mg`.

```
void sv_setpviv(SV* sv, IV num)
```

**sv\_setpviv\_mg**

Like `sv_setpviv`, but also handles 'set' magic.

```
void sv_setpviv_mg(SV *sv, IV iv)
```

**sv\_setpvn**

Copies a string into an SV. The `len` parameter indicates the number of bytes to be copied. If the `ptr` argument is NULL the SV will become undefined. Does not handle 'set' magic. See `sv_setpvn_mg`.

```
void sv_setpvn(SV* sv, const char* ptr, STRLEN len)
```

**sv\_setpvn\_mg**

Like `sv_setpvn`, but also handles 'set' magic.

```
void sv_setpvn_mg(SV *sv, const char *ptr, STRLEN len)
```

**sv\_setpv\_mg**

Like `sv_setpv`, but also handles 'set' magic.

```
void sv_setpv_mg(SV *sv, const char *ptr)
```

### sv\_setref\_iv

Copies an integer into a new SV, optionally blessing the SV. The `rv` argument will be upgraded to an RV. That RV will be modified to point to the new SV. The `classname` argument indicates the package for the blessing. Set `classname` to `Nullch` to avoid the blessing. The new SV will have a reference count of 1, and the RV will be returned.

```
SV* sv_setref_iv(SV* rv, const char* classname, IV iv)
```

### sv\_setref\_nv

Copies a double into a new SV, optionally blessing the SV. The `rv` argument will be upgraded to an RV. That RV will be modified to point to the new SV. The `classname` argument indicates the package for the blessing. Set `classname` to `Nullch` to avoid the blessing. The new SV will have a reference count of 1, and the RV will be returned.

```
SV* sv_setref_nv(SV* rv, const char* classname, NV nv)
```

### sv\_setref\_pv

Copies a pointer into a new SV, optionally blessing the SV. The `rv` argument will be upgraded to an RV. That RV will be modified to point to the new SV. If the `pv` argument is `NULL` then `PL_sv_undef` will be placed into the SV. The `classname` argument indicates the package for the blessing. Set `classname` to `Nullch` to avoid the blessing. The new SV will have a reference count of 1, and the RV will be returned.

Do not use with other Perl types such as HV, AV, SV, CV, because those objects will become corrupted by the pointer copy process.

Note that `sv_setref_pvn` copies the string while this copies the pointer.

```
SV* sv_setref_pv(SV* rv, const char* classname, void* pv)
```

### sv\_setref\_pvn

Copies a string into a new SV, optionally blessing the SV. The length of the string must be specified with `n`. The `rv` argument will be upgraded to an RV. That RV will be modified to point to the new SV. The `classname` argument indicates the package for the blessing. Set `classname` to `Nullch` to avoid the blessing. The new SV will have a reference count of 1, and the RV will be returned.

Note that `sv_setref_pv` copies the pointer while this copies the string.

```
SV* sv_setref_pvn(SV* rv, const char* classname, char* pv, STRLEN n)
```

### sv\_setref\_uv

Copies an unsigned integer into a new SV, optionally blessing the SV. The `rv` argument will be upgraded to an RV. That RV will be modified to point to the new SV. The `classname` argument indicates the package for the blessing. Set `classname` to `Nullch` to avoid the blessing. The new SV will have a reference count of 1, and the RV will be returned.

```
SV* sv_setref_uv(SV* rv, const char* classname, UV uv)
```

### sv\_setsv

Copies the contents of the source SV `ssv` into the destination SV `dsv`. The source SV may be destroyed if it is mortal, so don't use this function if the source SV needs to be reused. Does not handle 'set' magic. Loosely speaking, it performs a copy-by-value, obliterating any previous content of the destination.

You probably want to use one of the assortment of wrappers, such as `SvSetSV`,



SvSetSV\_nosteal, SvSetMagicSV and SvSetMagicSV\_nosteal.

```
void sv_setsv(SV* dsv, SV* ssv)
```

### sv\_setsv\_flags

Copies the contents of the source SV *ssv* into the destination SV *dsv*. The source SV may be destroyed if it is mortal, so don't use this function if the source SV needs to be reused. Does not handle 'set' magic. Loosely speaking, it performs a copy-by-value, obliterating any previous content of the destination. If the *flags* parameter has the `SV_GMAGIC` bit set, will `mg_get` on *ssv* if appropriate, else not. If the *flags* parameter has the `NOSTEAL` bit set then the buffers of temps will not be stolen. `<sv_setsv>` and `sv_setsv_nomg` are implemented in terms of this function.

You probably want to use one of the assortment of wrappers, such as `SvSetSV`, `SvSetSV_nosteal`, `SvSetMagicSV` and `SvSetMagicSV_nosteal`.

This is the primary function for copying scalars, and most other copy-ish functions and macros use this underneath.

```
void sv_setsv_flags(SV* dsv, SV* ssv, I32 flags)
```

### sv\_setsv\_mg

Like `sv_setsv`, but also handles 'set' magic.

```
void sv_setsv_mg(SV *dstr, SV *sstr)
```

### sv\_setsv\_nomg

Like `sv_setsv` but doesn't process magic.

```
void sv_setsv_nomg(SV* dsv, SV* ssv)
```

### sv\_setuv

Copies an unsigned integer into the given SV, upgrading first if necessary. Does not handle 'set' magic. See also `sv_setuv_mg`.

```
void sv_setuv(SV* sv, UV num)
```

### sv\_setuv\_mg

Like `sv_setuv`, but also handles 'set' magic.

```
void sv_setuv_mg(SV *sv, UV u)
```

### sv\_taint

Taint an SV. Use `SvTAINTED_on` instead. `void sv_taint(SV* sv)`

### sv\_tainted

Test an SV for taintedness. Use `SvTAINTED` instead. `bool sv_tainted(SV* sv)`

### sv\_true

Returns true if the SV has a true value by Perl's rules. Use the `SvTRUE` macro instead, which may call `sv_true()` or may instead use an in-line version.

```
I32 sv_true(SV *sv)
```

### sv\_unmagic

Removes all magic of type *type* from an SV.

```
int sv_unmagic(SV* sv, int type)
```

### sv\_unref

Unsets the RV status of the SV, and decrements the reference count of whatever was being referenced by the RV. This can almost be thought of as a reversal of `newSVrv`. This is `sv_unref_flags` with the `flag` being zero. See `SvROK_off`.

```
void sv_unref(SV* sv)
```

### sv\_unref\_flags

Unsets the RV status of the SV, and decrements the reference count of whatever was being referenced by the RV. This can almost be thought of as a reversal of `newSVrv`. The `cflags` argument can contain `SV_IMMEDIATE_UNREF` to force the reference count to be decremented (otherwise the decrementing is conditional on the reference count being different from one or the reference being a readonly SV). See `SvROK_off`.

```
void sv_unref_flags(SV* sv, U32 flags)
```

### sv\_untaint

Untaint an SV. Use `SvTAINTED_off` instead. `void sv_untaint(SV* sv)`

### sv\_upgrade

Upgrade an SV to a more complex form. Generally adds a new body type to the SV, then copies across as much information as possible from the old body. You generally want to use the `SvUPGRADE` macro wrapper. See also `svtype`.

```
bool sv_upgrade(SV* sv, U32 mt)
```

### sv\_usepvn

Tells an SV to use `ptr` to find its string value. Normally the string is stored inside the SV but `sv_usepvn` allows the SV to use an outside string. The `ptr` should point to memory that was allocated by `malloc`. The string length, `len`, must be supplied. This function will realloc the memory pointed to by `ptr`, so that pointer should not be freed or used by the programmer after giving it to `sv_usepvn`. Does not handle 'set' magic. See `sv_usepvn_mg`.

```
void sv_usepvn(SV* sv, char* ptr, STRLEN len)
```

### sv\_usepvn\_mg

Like `sv_usepvn`, but also handles 'set' magic.

```
void sv_usepvn_mg(SV *sv, char *ptr, STRLEN len)
```

### sv\_utf8\_decode

If the PV of the SV is an octet sequence in UTF-8 and contains a multiple-byte character, the `SvUTF8` flag is turned on so that it looks like a character. If the PV contains only single-byte characters, the `SvUTF8` flag stays being off. Scans PV for validity and returns false if the PV is invalid UTF-8.

NOTE: this function is experimental and may change or be removed without notice.

```
bool sv_utf8_decode(SV *sv)
```

### sv\_utf8\_downgrade

Attempts to convert the PV of an SV from characters to bytes. If the PV contains a character beyond byte, this conversion will fail; in this case, either returns false or, if `fail_ok` is not true, croaks.

This is not as a general purpose Unicode to byte encoding interface: use the Encode extension for that.

NOTE: this function is experimental and may change or be removed without notice.

```
bool sv_utf8_downgrade(SV *sv, bool fail_ok)
```

#### sv\_utf8\_encode

Converts the PV of an SV to UTF-8, but then turns the SvUTF8 flag off so that it looks like octets again.

```
void sv_utf8_encode(SV *sv)
```

#### sv\_utf8\_upgrade

Converts the PV of an SV to its UTF-8-encoded form. Forces the SV to string form if it is not already. Always sets the SvUTF8 flag to avoid future validity checks even if all the bytes have hibit clear.

This is not as a general purpose byte encoding to Unicode interface: use the Encode extension for that.

```
STRLEN sv_utf8_upgrade(SV *sv)
```

#### sv\_utf8\_upgrade\_flags

Converts the PV of an SV to its UTF-8-encoded form. Forces the SV to string form if it is not already. Always sets the SvUTF8 flag to avoid future validity checks even if all the bytes have hibit clear. If `flags` has `SV_GMAGIC` bit set, will `mg_get` on `sv` if appropriate, else not. `sv_utf8_upgrade` and `sv_utf8_upgrade_nomg` are implemented in terms of this function.

This is not as a general purpose byte encoding to Unicode interface: use the Encode extension for that.

```
STRLEN sv_utf8_upgrade_flags(SV *sv, I32 flags)
```

#### sv\_uv

A private implementation of the `SvUVx` macro for compilers which can't cope with complex macro expressions. Always use the macro instead.

```
UV sv_uv(SV* sv)
```

#### sv\_vcatpvf

Processes its arguments like `vsprintf` and appends the formatted output to an SV. Does not handle 'set' magic. See `sv_vcatpvf_mg`.

Usually used via its frontend `sv_catpvf`.

```
void sv_vcatpvf(SV* sv, const char* pat, va_list* args)
```

#### sv\_vcatpvfn

Processes its arguments like `vsprintf` and appends the formatted output to an SV. Uses an array of SVs if the C style variable argument list is missing (NULL). When running with taint checks enabled, indicates via `maybe_tainted` if results are untrustworthy (often due to the use of locales).

XXX Except that it `maybe_tainted` is never assigned to.

Usually used via one of its frontends `sv_vcatpvf` and `sv_vcatpvf_mg`.

```
void sv_vcatpvfn(SV* sv, const char* pat, STRLEN patlen, va_list* args, SV** svargs, I32 svmax, bool *maybe_tainted)
```

**sv\_vcatpvf\_mg**

Like `sv_vcatpvf`, but also handles 'set' magic.

Usually used via its frontend `sv_catpvf_mg`.

```
void sv_vcatpvf_mg(SV* sv, const char* pat, va_list* args)
```

**sv\_vsetpvf**

Works like `sv_vcatpvf` but copies the text into the SV instead of appending it. Does not handle 'set' magic. See `sv_vsetpvf_mg`.

Usually used via its frontend `sv_setpvf`.

```
void sv_vsetpvf(SV* sv, const char* pat, va_list* args)
```

**sv\_vsetpvfn**

Works like `sv_vcatpvfn` but copies the text into the SV instead of appending it.

Usually used via one of its frontends `sv_vsetpvf` and `sv_vsetpvf_mg`.

```
void sv_vsetpvfn(SV* sv, const char* pat, STRLEN patlen,
va_list* args, SV** svargs, I32 svmax, bool *maybe_tainted)
```

**sv\_vsetpvf\_mg**

Like `sv_vsetpvf`, but also handles 'set' magic.

Usually used via its frontend `sv_setpvf_mg`.

```
void sv_vsetpvf_mg(SV* sv, const char* pat, va_list* args)
```

**Unicode Support****bytes\_from\_utf8**

Converts a string `s` of length `len` from UTF-8 into byte encoding. Unlike `utf8_to_bytes` but like `bytes_to_utf8`, returns a pointer to the newly-created string, and updates `len` to contain the new length. Returns the original string if no conversion occurs, `len` is unchanged. Do nothing if `is_utf8` points to 0. Sets `is_utf8` to 0 if `s` is converted or contains all 7bit characters.

NOTE: this function is experimental and may change or be removed without notice.

```
U8* bytes_from_utf8(U8 *s, STRLEN *len, bool *is_utf8)
```

**bytes\_to\_utf8**

Converts a string `s` of length `len` from ASCII into UTF-8 encoding. Returns a pointer to the newly-created string, and sets `len` to reflect the new length.

If you want to convert to UTF-8 from other encodings than ASCII, see `sv_recode_to_utf8()`.

NOTE: this function is experimental and may change or be removed without notice.

```
U8* bytes_to_utf8(U8 *s, STRLEN *len)
```

**ibcmp\_utf8**

Return true if the strings `s1` and `s2` differ case-insensitively, false if not (if they are equal case-insensitively). If `u1` is true, the string `s1` is assumed to be in UTF-8-encoded Unicode. If `u2` is true, the string `s2` is assumed to be in UTF-8-encoded Unicode. If `u1` or `u2` are false, the respective string is assumed to be in native 8-bit encoding.

If the `pe1` and `pe2` are non-NULL, the scanning pointers will be copied in there (they

will point at the beginning of the *next* character). If the pointers behind `pe1` or `pe2` are non-NULL, they are the end pointers beyond which scanning will not continue under any circumstances. If the byte lengths `l1` and `l2` are non-zero, `s1+l1` and `s2+l2` will be used as goal end pointers that will also stop the scan, and which qualify towards defining a successful match: all the scans that define an explicit length must reach their goal pointers for a match to succeed).

For case-insensitiveness, the "casefolding" of Unicode is used instead of upper/lowercasing both the characters, see <http://www.unicode.org/unicode/reports/tr21/> (Case Mappings).

```
I32 ibcmp_utf8(const char* a, char **pe1, UV l1, bool u1, const
char* b, char **pe2, UV l2, bool u2)
```

### is\_utf8\_char

Tests if some arbitrary number of bytes begins in a valid UTF-8 character. Note that an INVARIANT (i.e. ASCII) character is a valid UTF-8 character. The actual number of bytes in the UTF-8 character will be returned if it is valid, otherwise 0.

```
STRLEN is_utf8_char(U8 *p)
```

### is\_utf8\_string

Returns true if first `len` bytes of the given string form a valid UTF-8 string, false otherwise. Note that 'a valid UTF-8 string' does not mean 'a string that contains code points above 0x7F encoded in UTF-8' because a valid ASCII string is a valid UTF-8 string.

See also `is_utf8_string_loclen()` and `is_utf8_string_loc()`.

```
bool is_utf8_string(U8 *s, STRLEN len)
```

### is\_utf8\_string\_loc

Like `is_utf8_string()` but stores the location of the failure (in the case of "utf8ness failure") or the location `s+len` (in the case of "utf8ness success") in the `ep`.

See also `is_utf8_string_loclen()` and `is_utf8_string()`.

```
bool is_utf8_string_loc(U8 *s, STRLEN len, U8 **p)
```

### is\_utf8\_string\_loclen

Like `is_utf8_string()` but stores the location of the failure (in the case of "utf8ness failure") or the location `s+len` (in the case of "utf8ness success") in the `ep`, and the number of UTF-8 encoded characters in the `e1`.

See also `is_utf8_string_loc()` and `is_utf8_string()`.

```
bool is_utf8_string_loclen(const U8 *s, STRLEN len, const U8
**ep, STRLEN *e1)
```

### pv\_uni\_display

Build to the scalar `dsv` a displayable version of the string `spv`, length `len`, the displayable version being at most `pvlm` bytes long (if longer, the rest is truncated and "... " will be appended).

The `flags` argument can have `UNI_DISPLAY_ISPRINT` set to display `isPRINT()`able characters as themselves, `UNI_DISPLAY_BACKSLASH` to display the `\\[nrfta\\]` as the backslashed versions (like `'\n'`) (`UNI_DISPLAY_BACKSLASH` is preferred over `UNI_DISPLAY_ISPRINT` for `\\`). `UNI_DISPLAY_QQ` (and its alias `UNI_DISPLAY_REGEX`) have both `UNI_DISPLAY_BACKSLASH` and

UNI\_DISPLAY\_ISPRINT turned on.

The pointer to the PV of the dsv is returned.

```
char* pv_uni_display(SV *dsv, U8 *spv, STRLEN len, STRLEN
pvlm, UV flags)
```

### sv\_cat\_decode

The encoding is assumed to be an Encode object, the PV of the ssv is assumed to be octets in that encoding and decoding the input starts from the position which (PV + \*offset) pointed to. The dsv will be concatenated the decoded UTF-8 string from ssv. Decoding will terminate when the string tstr appears in decoding output or the input ends on the PV of the ssv. The value which the offset points will be modified to the last input position on the ssv.

Returns TRUE if the terminator was found, else returns FALSE.

```
bool sv_cat_decode(SV* dsv, SV *encoding, SV *ssv, int *offset,
char* tstr, int tlen)
```

### sv\_recode\_to\_utf8

The encoding is assumed to be an Encode object, on entry the PV of the sv is assumed to be octets in that encoding, and the sv will be converted into Unicode (and UTF-8).

If the sv already is UTF-8 (or if it is not POK), or if the encoding is not a reference, nothing is done to the sv. If the encoding is not an Encode::XS Encoding object, bad things will happen. (See *lib/encoding.pm* and *Encode*).

The PV of the sv is returned.

```
char* sv_recode_to_utf8(SV* sv, SV *encoding)
```

### sv\_uni\_display

Build to the scalar dsv a displayable version of the scalar sv, the displayable version being at most pvlm bytes long (if longer, the rest is truncated and "... " will be appended).

The flags argument is as in pv\_uni\_display().

The pointer to the PV of the dsv is returned.

```
char* sv_uni_display(SV *dsv, SV *ssv, STRLEN pvlm, UV flags)
```

### to\_utf8\_case

The "p" contains the pointer to the UTF-8 string encoding the character that is being converted.

The "ustrp" is a pointer to the character buffer to put the conversion result to. The "lenp" is a pointer to the length of the result.

The "swashp" is a pointer to the swash to use.

Both the special and normal mappings are stored lib/unicore/To/Foo.pl, and loaded by SWASHGET, using lib/utf8\_heavy.pl. The special (usually, but not always, a multicharacter mapping), is tried first.

The "special" is a string like "utf8::ToSpecLower", which means the hash %utf8::ToSpecLower. The access to the hash is through Perl\_to\_utf8\_case().

The "normal" is a string like "ToLower" which means the swash %utf8::ToLower.

```
UV to_utf8_case(U8 *p, U8* ustrp, STRLEN *lenp, SV **swashp,
char *normal, char *special)
```

### to\_utf8\_fold

Convert the UTF-8 encoded character at `p` to its foldcase version and store that in UTF-8 in `ustrp` and its length in bytes in `lenp`. Note that the `ustrp` needs to be at least `UTF8_MAXBYTES_CASE+1` bytes since the foldcase version may be longer than the original character (up to three characters).

The first character of the foldcased version is returned (but note, as explained above, that there may be more.)

```
UV to_utf8_fold(U8 *p, U8* ustrp, STRLEN *lenp)
```

### to\_utf8\_lower

Convert the UTF-8 encoded character at `p` to its lowercase version and store that in UTF-8 in `ustrp` and its length in bytes in `lenp`. Note that the `ustrp` needs to be at least `UTF8_MAXBYTES_CASE+1` bytes since the lowercase version may be longer than the original character.

The first character of the lowercased version is returned (but note, as explained above, that there may be more.)

```
UV to_utf8_lower(U8 *p, U8* ustrp, STRLEN *lenp)
```

### to\_utf8\_title

Convert the UTF-8 encoded character at `p` to its titlecase version and store that in UTF-8 in `ustrp` and its length in bytes in `lenp`. Note that the `ustrp` needs to be at least `UTF8_MAXBYTES_CASE+1` bytes since the titlecase version may be longer than the original character.

The first character of the titlecased version is returned (but note, as explained above, that there may be more.)

```
UV to_utf8_title(U8 *p, U8* ustrp, STRLEN *lenp)
```

### to\_utf8\_upper

Convert the UTF-8 encoded character at `p` to its uppercase version and store that in UTF-8 in `ustrp` and its length in bytes in `lenp`. Note that the `ustrp` needs to be at least `UTF8_MAXBYTES_CASE+1` bytes since the uppercase version may be longer than the original character.

The first character of the uppercased version is returned (but note, as explained above, that there may be more.)

```
UV to_utf8_upper(U8 *p, U8* ustrp, STRLEN *lenp)
```

### utf8n\_to\_uvchr

Returns the native character value of the first character in the string `s` which is assumed to be in UTF-8 encoding; `retlen` will be set to the length, in bytes, of that character.

Allows length and flags to be passed to low level routine.

```
UV utf8n_to_uvchr(U8 *s, STRLEN curlen, STRLEN *retlen, U32 flags)
```

### utf8n\_to\_uvuni

Bottom level UTF-8 decode routine. Returns the unicode code point value of the first character in the string `s` which is assumed to be in UTF-8 encoding and no longer than `curlen`; `retlen` will be set to the length, in bytes, of that character.

If `s` does not point to a well-formed UTF-8 character, the behaviour is dependent on

the value of `flags`: if it contains `UTF8_CHECK_ONLY`, it is assumed that the caller will raise a warning, and this function will silently just set `retlen` to `-1` and return zero. If the `flags` does not contain `UTF8_CHECK_ONLY`, warnings about malformations will be given, `retlen` will be set to the expected length of the UTF-8 character in bytes, and zero will be returned.

The `flags` can also contain various flags to allow deviations from the strict UTF-8 encoding (see *utf8.h*).

Most code should use `utf8_to_uvchr()` rather than call this directly.

```
UV utf8n_to_uvuni(U8 *s, STRLEN curlen, STRLEN *retlen, U32 flags)
```

#### utf8\_distance

Returns the number of UTF-8 characters between the UTF-8 pointers `a` and `b`.

**WARNING:** use only if you *\*know\** that the pointers point inside the same UTF-8 buffer.

```
IV utf8_distance(U8 *a, U8 *b)
```

#### utf8\_hop

Return the UTF-8 pointer `s` displaced by `off` characters, either forward or backward.

**WARNING:** do not use the following unless you *\*know\** `off` is within the UTF-8 data pointed to by `s` *\*and\** that on entry `s` is aligned on the first byte of character or just after the last byte of a character.

```
U8* utf8_hop(U8 *s, I32 off)
```

#### utf8\_length

Return the length of the UTF-8 char encoded string `s` in characters. Stops at `e` (inclusive). If `e < s` or if the scan would end up past `e`, croaks.

```
STRLEN utf8_length(U8* s, U8 *e)
```

#### utf8\_to\_bytes

Converts a string `s` of length `len` from UTF-8 into byte encoding. Unlike `bytes_to_utf8`, this over-writes the original string, and updates `len` to contain the new length. Returns zero on failure, setting `len` to `-1`.

**NOTE:** this function is experimental and may change or be removed without notice.

```
U8* utf8_to_bytes(U8 *s, STRLEN *len)
```

#### utf8\_to\_uvchr

Returns the native character value of the first character in the string `s` which is assumed to be in UTF-8 encoding; `retlen` will be set to the length, in bytes, of that character.

If `s` does not point to a well-formed UTF-8 character, zero is returned and `retlen` is set, if possible, to `-1`.

```
UV utf8_to_uvchr(U8 *s, STRLEN *retlen)
```

#### utf8\_to\_uvuni

Returns the Unicode code point of the first character in the string `s` which is assumed to be in UTF-8 encoding; `retlen` will be set to the length, in bytes, of that character.

This function should only be used when returned UV is considered an index into the



Unicode semantic tables (e.g. swashes).

If *s* does not point to a well-formed UTF-8 character, zero is returned and *retlen* is set, if possible, to -1.

```
UV utf8_to_uvuni(U8 *s, STRLEN *retlen)
```

#### uvchr\_to\_utf8

Adds the UTF-8 representation of the Native codepoint *uv* to the end of the string *d*; *d* should be have at least `UTF8_MAXBYTES+1` free bytes available. The return value is the pointer to the byte after the end of the new character. In other words,

```
d = uvchr_to_utf8(d, uv);
```

is the recommended wide native character-aware way of saying

```
*(d++) = uv;
```

```
U8* uvchr_to_utf8(U8 *d, UV uv)
```

#### uvuni\_to\_utf8\_flags

Adds the UTF-8 representation of the Unicode codepoint *uv* to the end of the string *d*; *d* should be have at least `UTF8_MAXBYTES+1` free bytes available. The return value is the pointer to the byte after the end of the new character. In other words,

```
d = uvuni_to_utf8_flags(d, uv, flags);
```

or, in most cases,

```
d = uvuni_to_utf8(d, uv);
```

(which is equivalent to)

```
d = uvuni_to_utf8_flags(d, uv, 0);
```

is the recommended Unicode-aware way of saying

```
*(d++) = uv;
```

```
U8* uvuni_to_utf8_flags(U8 *d, UV uv, UV flags)
```

## Variables created by `xsubpp` and `xsubpp` internal functions

### ax

Variable which is setup by `xsubpp` to indicate the stack base offset, used by the `ST`, `XSpREPUSH` and `XSPRETURN` macros. The `dMARK` macro must be called prior to setup the `MARK` variable.

```
I32 ax
```

### CLASS

Variable which is setup by `xsubpp` to indicate the class name for a C++ XS constructor. This is always a `char*`. See [THIS](#).

```
char* CLASS
```

### dAX

Sets up the `ax` variable. This is usually handled automatically by `xsubpp` by calling `dXSARGS`.

```
dAX;
```

**dAXMARK**

Sets up the `ax` variable and stack marker variable `mark`. This is usually handled automatically by `xsubpp` by calling `dXSARGS`.

```
dAXMARK;
```

**dITEMS**

Sets up the `items` variable. This is usually handled automatically by `xsubpp` by calling `dXSARGS`.

```
dITEMS;
```

**dXSARGS**

Sets up stack and mark pointers for an XSUB, calling `dSP` and `dMARK`. Sets up the `ax` and `items` variables by calling `dAX` and `dITEMS`. This is usually handled automatically by `xsubpp`.

```
dXSARGS;
```

**dXSI32**

Sets up the `ix` variable for an XSUB which has aliases. This is usually handled automatically by `xsubpp`.

```
dXSI32;
```

**items**

Variable which is setup by `xsubpp` to indicate the number of items on the stack. See "*Variable-length Parameter Lists*" in *perlxs*.

```
I32 items
```

**ix**

Variable which is setup by `xsubpp` to indicate which of an XSUB's aliases was used to invoke it. See "*The ALIAS: Keyword*" in *perlxs*.

```
I32 ix
```

**newXSproto**

Used by `xsubpp` to hook up XSUBs as Perl subs. Adds Perl prototypes to the subs.

**RETVAL**

Variable which is setup by `xsubpp` to hold the return value for an XSUB. This is always the proper type for the XSUB. See "*The RETVAL Variable*" in *perlxs*.

```
(whatever) RETVAL
```

**ST**

Used to access elements on the XSUB's stack.

```
SV* ST(int ix)
```

**THIS**

Variable which is setup by `xsubpp` to designate the object in a C++ XSUB. This is always the proper type for the C++ object. See `CLASS` and "*Using XS With C++*" in *perlxs*.

```
(whatever) THIS
```

**XS**

Macro to declare an XSUB and its C parameter list. This is handled by `xsubpp`.

**XS\_VERSION**

The version identifier for an XS module. This is usually handled automatically by `ExtUtils::MakeMaker`. See `XS_VERSION_BOOTCHECK`.

**XS\_VERSION\_BOOTCHECK**

Macro to verify that a PM module's `$VERSION` variable matches the XS module's `XS_VERSION` variable. This is usually handled automatically by `xsubpp`. See "*The VERSIONCHECK: Keyword*" in *perlx*.

```
XS_VERSION_BOOTCHECK;
```

**Warning and Dieing****croak**

This is the XSUB-writer's interface to Perl's `die` function. Normally call this function the same way you call the C `printf` function. Calling `croak` returns control directly to Perl, sidestepping the normal C order of execution. See `warn`.

If you want to throw an exception object, assign the object to `$@` and then pass `Nullch` to `croak()`:

```
errsv = get_sv("@", TRUE);
sv_setsv(errsv, exception_object);
croak(Nullch);
```

```
void croak(const char* pat, ...)
```

**warn**

This is the XSUB-writer's interface to Perl's `warn` function. Call this function the same way you call the C `printf` function. See `croak`.

```
void warn(const char* pat, ...)
```

**AUTHORS**

Until May 1997, this document was maintained by Jeff Okamoto <okamoto@corp.hp.com>. It is now maintained as part of Perl itself.

With lots of help and suggestions from Dean Roehrich, Malcolm Beattie, Andreas Koenig, Paul Hudson, Ilya Zakharevich, Paul Marquess, Neil Bowers, Matthew Green, Tim Bunce, Spider Boardman, Ulrich Pfeifer, Stephen McCamant, and Gurusamy Sarathy.

API Listing originally by Dean Roehrich <roehrich@cray.com>.

Updated to be autogenerated from comments in the source by Benjamin Stuhl.

**SEE ALSO**

`perlguts(1)`, `perlx(1)`, `perlxstut(1)`, `perlintern(1)`